

A decorative vertical bar on the left side of the page, composed of numerous thin, vertical lines of varying shades of gray.

Logic|⁵

Music Production Software

Introduction Manual

>> Version 5.0, January 2002

>> English Edition

License Agreement

Important! Please read this licence agreement carefully before opening the disk seal! Opening of the disk seal and use of this package indicates your agreement to the following terms and conditions. Emagic grants you a non-exclusive, non-transferable license to use the software in this package.

You may:

1. use the software on a single machine.
2. make one copy of the software solely for back-up purposes.

You may not:

1. make copies of the user manual or the software except as expressly provided for in this agreement.
2. make alterations or modifications to the software or any copy, or otherwise attempt to discover the source code of the software.
3. sub-license, lease, lend, rent or grant other rights in all or any copy to others.

Except to the extent prohibited by applicable law, all implied warranties made by Emagic in connection with this manual and software are limited in duration to the minimum statutory guarantee period in your state or country from the date of original purchase, and no warranties, whether express or implied, shall apply to this product after said period. This warranty is not transferable-it applies only to the original purchaser of the software. Emagic makes no warranty, either express or implied, with respect to this software, its quality, performance, merchantability or fitness for a particular purpose. As a result, this software is sold "as is", and you, the purchaser, are assuming the entire risk as to quality and performance. In no event will Emagic be liable for any direct or indirect damages resulting from any defect in the software or documentation.

This agreement will terminate if you fail to comply with any term or condition in this agreement.

This agreement shall be governed by the laws of the Federal Republic of Germany.

This manual, copy-protection and software described herein are copyrighted © 1992—2002 by Emagic Soft- und Hardware GmbH, Halstenbeker Weg 96, 25462 Rellingen, Germany

Chapter 1	Welcome	
1.1	About the Introduction Manual and Reference Manual	10
1.2	For Those Who Hate Manuals	13
1.3	A Starting Point	13
1.4	What Is Logic?	14
1.5	Audio and MIDI	15
	MIDI.	15
	Audio.	19
	About Bits and Sampling Rates.	21
	About MIDI and Audio File Sizes.	22
1.6	Audio Tracks	22
1.7	MIDI Tracks	23
1.8	Logic Terminology	23
1.9	The Mouse.	25
	Basic Functions.	25
	Mouse Input	26
	Tools and the Toolbox.	28
1.10	Window Functions	32
	Working with Windows	33
	Links between Windows	37
1.11	Selection Techniques	38
	Selecting Individual Objects	39
	Selecting Several Objects	39
1.12	Edit Operations	41
	Undo	41
	The Clipboard	41
1.13	General Functions of the Editors.	43
	Opening Editors	43
	Control Output via MIDI.	43
	Automatic Scroll Functions	43
	Setting Locators by Objects	44
	Deleting Events	45
	Display Functions	45
1.14	Key Commands	46
	Special Keys	46
	Key Commands Window	47
1.15	Controlling Windows—Screensets	49
1.16	Song Administration	51
	New Song	51
	Loading a Song	51
	Checking/Repairing Songs	52
	Saving Songs	52
	Closing a Song.	52

Table of Contents

	Quitting the Program.....	52
1.17	The Transport Bar.....	53
	Transport Key Commands	54
	Simple Science.....	55
Chapter 2	The Ideal Workspace	
2.1	3 Dimensional Software	57
2.2	The Environment Concept	59
2.3	The Data Flow	60
	Getting Started	61
2.4	Your First Environment	70
	Instrument Objects.....	71
	Some Preparation.....	72
2.5	Construction Time	73
	Plain Vanilla Settings	74
	Quick Environment Setup	75
2.6	Manual Instrument Setup	77
	Input and Metronome Objects	77
	Setting up Single Instruments	78
	Setting up Multi Instruments	79
	Setting up Mapped Instruments	86
2.7	Creating Audio Objects	88
2.8	Setting up Tracks	94
2.9	Environment Controls.....	95
	Setting up a Single Fader	96
	How to Automate Faders	100
	Setting up a GM Mixer Object	104
2.10	Environment Processing	105
2.11	MIDI Meets Audio	111
Chapter 3	Using Logic	
3.1	Adapting the Tutorial Song.....	114
	Load the Tutorial Song	114
	General MIDI Tone Generator.....	115
	Non GM, Multi-Timbral Tone Generators	115
	Sounds and MIDI Channels	116
	Drum Kit	116
	Starting the Song.....	117
3.2	Overview	118
3.3	Tracks and Sequences.....	119

	Information Track and Instruments	120
3.4	The Arrange Window	121
	Parameters Area	121
3.5	Navigating the Song	126
	The Transport Bar	126
	Moving to Different Song Positions	127
	Display Current Song Position	129
	Zoom a Window Excerpt	129
	Cycle Mode	129
	Selection Techniques	131
3.6	Changing and Creating Sequences	132
	Quantize	132
	Loops	134
	Resizing a Sequence	136
	Moving a Sequence	137
	Undo/Redo	138
	Copying Sequences	139
	Transposing Sequences	140
	Your First Recording	142
	Song Settings	143
	Let's Record!	144
	Saving the Song	145
3.7	MIDI Event Editing	146
	The Event List Editor	146
	The Matrix Editor	149
	The Hyper Editor	153
	The Transform Window	154
	The Notation (Score) Editor	155
3.8	Audio Tracks and Regions	155
	Creating Audio Tracks	156
	Track Mixer with Audio Channels	156
	Changing the Track Mixer View	158
	Importing an Audio File	159
	Sample Editor	160
	The Audio Window	162
	The Digital Factory	164
	Making Your Own Audio Recordings	164
3.9	Mixer Functions	169
	Automatic Mixing	169
	Using the Equalizers	170
	Inserting Audio Effects	171
	The Plug-in Window	173
	Using the Effect Buses	176

Table of Contents


	What Sort of Effects Go Where?	178
	About Summed Levels	178
	Audio Instruments	179
	Plug-in Automation	182
3.10	More Files to Try Out	183
	Now It's Your Turn	184
Chapter 4	Mix Automation	
4.1	About the Mix Demo Song	186
	Load the Mix Demo Song	186
	Play the Mix Demo Song	187
	Song Screensets	187
4.2	Track Automation Basics	187
	Viewing Track Automation	188
	Important Information	188
4.3	Track Automation Menu	191
4.4	Track Automation Modes	193
4.5	On/Offline Automation	196
	Online or "Live" Automation	196
	Offline Automation	197
4.6	Automating Plug-in Parameters	197
	Effects "Slots"	198
4.7	Editing	199
	Handling Nodes	199
	Handling Lines	202
	Selection Handling	203
4.8	The Final Mix	205
	Bouncing—Procedure	206
	Bounce—Saving Resources	207
4.9	Audio Configuration	209
Chapter 5	Miscellaneous Info	
5.1	The Autoload Song	211
5.2	SoundDiver	212
	About Autolink	212
5.3	Logic Control	214
5.4	Synchronization	216
	Synchronization Tips	217

Chapter 1

Welcome

... to the Logic 5 Introduction Manual.

First up, we would like to congratulate you on your purchase. In choosing your version of the Logic line, you have selected the most widely used audio and MIDI production software in professional circles.



The diagram shows—in a counter-clockwise direction from the top left—the Arrange window with several audio regions and MIDI sequences, the Score editor, the Matrix editor and the Track Mixer.

1.1 About the Introduction Manual and Reference Manual

We have created this Introduction Manual with the intention of introducing you to many of Logic's features in a practical "hands-on" way. While you can certainly read the Introduction Manual on the beach or in your favorite easy chair, we would suggest that you take advantage of the accompanying song files supplied on your program CD-ROM. These files will assist you in quickly learning how to handle MIDI and audio information via a series of exercises and examples.

For those of you who have a keen interest in Logic's notation facilities, we have created an extensive Score Tutorial, which is available in electronic form on the program CD-ROM. You will also find a number of song files which will provide you with source material for the Score Tutorial.

We're sure that you're ready to "dive in" to Logic and start working through the remainder of the Introduction Manual, but before you do ...

We ask that you read the following sections in this chapter, which discuss the "basics" of Logic's user interface and key information on Logic's navigational aids. This information is essential reading as Logic offers a range of unique options for interaction with its user interface. You will need to be familiar with these techniques, and the terminology used, as this information forms the basis of the Introduction Manual and will help you to develop good working habits from the outset. This will accelerate your use of Logic and will make learning the program more enjoyable and simpler.

Important!

The various editing windows, functions and options which you will be introduced to throughout the Introduction Manual are explained in further detail in the Reference Manual. This manual is designed as a reference work. In other words, you can open a specific chapter on a specific editing window, setup task

etc. and find information on it. You will also discover a number of further small practical examples as you work your way through the Reference Manual which will enhance your understanding of features and functions. As a result, a number of techniques discussed in earlier chapters (of both this Introduction Manual and the Reference Manual) are repeated, but as the old adage goes, “practice makes perfect”.

We strongly recommend that you read the entire Reference Manual, in addition to this Introduction Manual. This Introduction Manual is designed to get you “up and running” with Logic quickly. It is not the final arbiter on all things Logic and does not cover all areas of the program in detail.

Important!

As you follow the Introduction Manual, you will create your own working “template” song file, which will be customized to meet your needs and tastes. This template will form the basis of your future work with Logic.

Needless to say, you will be introduced to a lot of new terminology as you’re reading through the Introduction Manual. This will be particularly noticeable throughout the early chapters. We will include explanations and diagrams throughout to help you understand the terms and functions. So, don’t sweat it if you encounter a term that you’re unfamiliar with—it will all fall into place as you continue reading. On this point, please read the Introduction Manual in the order that it is laid out. Many techniques that you will learn in one section are directly transferable to another. This way, you will have the best possible experience as you familiarize yourself with Logic.

We also ask that you pay special attention to comments that feature the “Important!” entry shown alongside the text. These are generally key points that will help you to understand a concept or fact about Logic. Where you see the “Tip” entry alongside the text, it usually indicates a shortcut, or some extra information that will help to accelerate your use of the program.

Important!




Tip

Menu Functions

Menu functions are written in this font: **Function**.

For functions which can be reached via hierarchical menus, the different menu levels are described as follows: **Menu > Menu entry > Function**.

Key Commands

When a function can be operated by a Key Command—that’s a computer keyboard shortcut—of the same name, you will see this symbol alongside the text. Many Key Commands make use of “modifier” keys—, **ctrl**, , and  in conjunction with other keys.



If the names of function and Key Command differ, or if a function is *only* available as a Key Command, its name will be printed as follows: *Key Command*.

We strongly recommend that you use Key Commands whenever possible. This will accelerate your use of Logic massively. As you are learning how to use the software, we ask that you use the Key Commands as you are introduced to them. This will aid you in remembering the Key Command and in your understanding of the function.

Tip


Additional information on Key Commands can be found in the *Key Commands* section, from page 46 onwards.

Options and Parameters

Options set in Logic’s Preferences, and the parameters in dialog boxes are printed as follows: **Parameters**.

Different parameter values are shown as follows: **Parameter value**.

Detailed Explanations

 Periodically, detailed explanations will be written for things which you don’t necessarily need to know, in order to understand how to use Logic. These are printed in this smaller font.

1.2 For Those Who Hate Manuals

If you're a reasonably proficient computer user who is familiar with audio and MIDI sequencing, you may wish to skip directly ahead to the *Using Logic* chapter, from page 113, to "get your hands dirty".

Chapters 1 and 2 cover the basics, and background information that you will need to know, in order to set up, and more fully use, your Logic system.

You can always refer back to these chapters as you're working through the "Using Logic" chapter, if necessary.

We do ask, however, that you *do* find the time to read these chapters at some stage, as this will help you to understand the basic structure and mechanics of the program. It will also make learning and using Logic more fun, and more productive.

1.3 A Starting Point

In writing this Introduction Manual, we needed to decide on a starting point. To this end, we ask that before you begin:

- Your computer meets the minimum requirements necessary to run your version of Logic.
- You have followed the separate Installation Guide and have correctly installed your version of Logic on your computer's hard disk.
- Your audio and MIDI interface hardware is correctly installed and has been identified and set up correctly in Logic.

For any hardware setup or software installation issues, please refer to your hardware manufacturer's installation guide(s) and the Troubleshooting section of the Logic Installation guide.

1.4 What Is Logic?

The Logic software is an integrated 32 Bit audio and MIDI recording system with flexible notation, fully automated mixing and native audio DSP effects processing facilities. You can:

- Record MIDI information via connected MIDI input devices, such as keyboards, and play back this information via any connected MIDI device, including keyboards, modules and sound cards with a built-in synthesizer chip.
- Create, arrange and edit MIDI songs, and print out musical notation via a printer connected to your computer.
- Digitally record acoustic and electric instruments or vocal performances into your songs, and process these audio recordings through Logic's in-built real-time effects.
- Add fully functional software synthesizers and samplers such as Emagic's **ES 1**, **ES 2**, **EUP 88** and **EKS 24**, or third-party VST 2.0 instruments to your copy of Logic. It should be noted that Logic ships with three software synthesizers, to get you started.
- Mix your MIDI and audio tracks, including effects and software-based instrument settings, via a sophisticated total recall mix automation system.
- Bounce all audio data, including effects and mix automation settings, to a stereo (or multiple Surround format) file(s) for mastering or further processing.

Logic incorporates the functionality normally found in an entire professional audio production studio. All within an intuitive user interface and all within your computer.

1.5 Audio and MIDI

Now that you know Logic can record and play back both MIDI and audio information, we have included the following which offers a brief and easy to understand description of both. If you already have an understanding of how MIDI and digital audio recording systems work, you can skip ahead to the *Audio Tracks* section, from page 22 onwards.

MIDI

MIDI is an acronym for Musical Instrument Digital Interface. To break this down further—the “Musical Instrument” part of MIDI refers to electronic musical instruments such as synthesizers, samplers and even MIDI guitars. The “Digital Interface” part sounds technical, but really isn’t.

Basically, MIDI’s “Digital Interface” is broken down into two components.

1. MIDI is a computer-based language—and as you probably know, computers talk “digitally”. MIDI keyboards, modules and cards are actually computers in disguise.
2. MIDI’s “Interface” is just that. MIDI is a hardware standard which consists of a set of physical connectors labeled IN, OUT, and THRU. You will find one or more of these connectors on all MIDI devices, such as keyboards etc.

The MIDI Language

The “language” of MIDI is understood by all MIDI devices. The purpose of the language is to translate your musical performance into information that can be understood by a computer. (Don’t forget that MIDI keyboards and modules are actually computers in disguise).

When you play your keyboard, or Logic is playing a MIDI song file, MIDI information which *describes* your performance is transmitted as a string of “MIDI messages”. These instructions tell any connected synthesizer, soundcard etc. *how* to play a piece of music. The synthesizer, module etc. receiving the MIDI data actually generates the sounds which you hear.

MIDI does not send sounds. It only sends instructions.

Important!

The MIDI Connection

MIDI, as mentioned, is also a hardware “interface” which consists of a standardized set of connectors labeled IN, OUT, and THRU.

MIDI connectors consist of a round socket with 5 holes arranged in a semicircle. MIDI cables, used for connecting MIDI devices have a matching plug with 5 pins. Only three of the pins actually carry information.

MIDI only works in one direction on each connector. If you want your MIDI keyboard to send messages *to*, and receive messages *from* Logic, you must connect *two* cables.

Here’s the way your MIDI connections must be made, in order to work:

- MIDI OUT connectors must be connected to MIDI IN connectors on the receiving device.
- MIDI IN connectors must be connected to MIDI OUTs

If you connect a MIDI OUT to another MIDI OUT or a MIDI IN to another MIDI IN, no communication will happen, and your MIDI system won’t work.

The MIDI THRU connector is not found on all MIDI devices. It simply mirrors the MIDI messages arriving at the MIDI input connector, and allows you to “daisy-chain” more MIDI devices. Before doing this, read the section on MIDI channels, which is very important when chaining MIDI keyboards, modules etc.

The “MIDI messages” are sent from a MIDI controller such as a keyboard or sequencer—i.e. Logic—via the MIDI OUT connector. The device (MIDI synth or sound module) receiving the MIDI messages at its MIDI IN connector, responds to these messages by playing sounds.

Remember, MIDI does not send sounds. It sends instructions on how, what and when to play.

Many MIDI keyboards include both the keyboard controller and MIDI sound module functions within the same unit. In these units, there’s an internal MIDI link between the keyboard and sound module. This internal link can be enabled or disabled by setting LOCAL ON or OFF—on the keyboard itself.

Tip

When using your MIDI keyboard with Logic, and the keyboard is acting as both controller and sound module, you should set LOCAL to OFF. Doing so avoids “it sounds like my notes are doubled or flanging” types of problems.

If your keyboard is simply acting as an input device, and you don’t want to use its sounds (or it doesn’t have any, as is the case with controller keyboards), you simply need to connect it’s MIDI OUT to the MIDI IN on your computer. Logic will take care of the “channels”, which we’re just about to take a look at.

MIDI Channels

MIDI is divided into 16 logical “channels”. Each channel is identified by a special channel number message that is sent with the other MIDI messages. Most keyboards can generally be set to transmit on any one of the 16 MIDI channels. A MIDI sound source—like your synthesizer, sound module or sound-card—can be set to receive on a specific, or multiple, MIDI Channel(s).

Devices capable of receiving on multiple MIDI channels simultaneously are said to be “multi-timbral”. The term literally means “many sounds”, which can be a little confusing, as most synthesizers are obviously capable of producing many

sounds. Not all synthesizers, however, are capable of producing many sounds at the one time. This capability means that a suitably equipped MIDI keyboard, module or soundcard could be used to produce all of the drum, bass, piano, string and brass sounds in a performance.

In this scenario, each part or instrument—drums, piano, strings etc.—will be assigned to a specific MIDI channel. Given the 16 logical MIDI channels available to each MIDI port and a multi-timbral synthesizer, up to 16 different “instruments” can be played simultaneously. Most modern MIDI keyboards, modules and sound cards are multi-timbral.

In *all* MIDI systems, the sound module must be set to receive on the channel (or channels in multi-timbral devices) which match the channel(s) that the keyboard controller (or Logic) is transmitting on, in order to play sounds. If the channels do not match, the receiving device will not play.

Tip

As an example: Imagine a 4-way multi-timbral device (a device capable of receiving on 4 MIDI channels simultaneously) is receiving song data from Logic with tracks assigned to channels 1, 2, 4 and 5.

The device itself is set to receive on channels 4 to 8. In this case, only the song’s MIDI data sent on channels 4 and 5 would be “seen” by the device and subsequently played. The MIDI data sent on channels 1 and 2 would be ignored.

As you can see from the above example, each channel needs to be “tuned in” to a corresponding channel sent from Logic. This, if you use a little imagination, is not unlike tuning in a TV or radio channel. If the channel isn’t tuned properly, you won’t see or hear anything ... and neither will your sound module.

Audio

Audio, as a term, basically refers to any sound that you can hear. In the physical, as opposed to computer world, this is known as *Analog Audio*. When Logic records analog audio signals via an audio interface connected to, or installed in, your computer, the audio is converted into digital information. This information is stored as a *Digital Audio* file on your computer's hard disk.

As with MIDI, the “Digital Audio” part sounds technical, but really isn't. As discussed earlier, computers talk “digitally” and need to deal with analog audio signals as digital information.

Unlike MIDI, digital audio files are actually recordings of sounds, *not* an instruction language.

Important!

Digital and Analog Recording

While digital audio recording is similar in concept to analog recordings made on tape, the technical differences are significant. For much of the 20th century, analog tape recordings have been used for the storage of audio performances—spoken, sung and played.

The analog tape medium (i.e. the tape itself) is a thin plastic strip coated in tiny metal particles. It is usually stored on a roll or spool or as a cassette tape, which you're probably familiar with.

The process of analog tape recording involves the transmission of small electrical charges, sent to the magnetic “heads” of a tape recorder. Changes to the strength of these charges alter the magnetic fields generated by the heads and rearrange the positions of the metal particles on the tape. Needless to say, this is a less than precise science. Due to the randomness involved in the rearrangement of magnetic particles on tape (and other technical reasons), the recordings are said to be “analogous”—i.e. similar to the actual performance.

Digital recording, on the other hand, is much less random. Analog performances are converted to digital audio files via the ADC (Analog to Digital Converter) of the audio interface. These files, like all computer files, are stored “digitally”—i.e. as a series of ones and zeroes. Provided the source material and levels remain consistent, digital recordings will be virtually identical each time they are made.

In a copying situation—i.e. tape to tape—there is no comparison between analog and digital recordings. Each subsequent copy of an analog recording becomes noisier and less like the source material. This is the “random” factor of the magnetic particles becoming less like the original each time a copy is made.

Digital audio files, on the other hand, can be copied any number of times, with each subsequent copy adding no noise.

On a more practical level, digital audio files stored on hard disk have the following advantages over analog audio stored on tape.

- Digital audio can be cut, copied and pasted freely from location to location. Could you imagine physically cutting a stereo analog recording—i.e. a tape—into even four or five segments and splicing them back together?
- You can move to any spot in a digital audio file almost instantly rather than waiting for the tedious mechanical rewinding and fast forwarding of an analog tape machine.
- You can process digital audio in ways that are simply impossible with analog audio. As one example, it is possible to adjust the pitch of a digital audio file without changing its speed.

Digital Conversions

When an analog audio signal arrives at the inputs of your computer’s audio interface, it must be converted into digital information before the computer can deal with it. This process is called “analog to digital conversion” and is handled by the Analog to Digital Converter (ADC) of your audio interface/soundcard.

At the other end of the signal path, the digital signal needs to be reconverted into an analog signal so that it can be listened to through analog audio playback systems—i.e. an amplifier and speakers. This process is called “digital to analog conversion” and is dealt with by the Digital to Analog Converter (DAC) of your audio interface/soundcard.

About Bits and Sampling Rates

When recording a sound into your computer, the ADC of your audio interface takes a “sample” of the sound source, a specific number of times per second. This is known as the “sample rate”, which is measured in kHz or so-many thousand samples per second. The higher the rate, the more samples the AD converter takes, and the more accurate the digital representation of the sound will be.

Put another way, imagine each sample to be a photograph of a concert that you were trying to describe to a friend. If you had taken one photo every 10 minutes, you’d find it hard to describe the great light show. If you took a thousand photos during that 10 minutes, your friend could easily see what happened. This increased “rate”, or number of photos (i.e. samples), gives a far more accurate overall picture of what happened. This is how sampling works. The more “sonic photos” taken, the more accurately the sound is represented over time.

The sampling resolution—that’s the “bit” thing—is the accuracy or precision of the measuring scale used to store the numbers of each sample. Remember that computers store audio files as digital information—a series of ones and zeroes. There are three resolutions commonly in use: 8, 16 and 24 bits. 24 bit systems are more expensive and are used extensively in DVD audio and film production.

To give you an idea of the relevance of the sampling resolution, imagine two people are building a house. One is using a tape measure marked to the nearest foot. The other has a tape measure marked to the nearest inch. Although the house built with the tape measure accurate to the nearest foot may not fall down, the one using the finer scale will build a more accurate house.

About MIDI and Audio File Sizes

Digital audio files consume a great deal of hard disk space. “CD quality” audio with 16-bit dynamic resolution and 44.1 kHz frequency resolution requires 5 megabytes (MB) of hard disk space for 1 minute of *monophonic* audio. For a *stereo* recording, this requirement is doubled, with a one minute audio file using 10 MB of storage space.

MIDI file data, on the other hand, is tiny. An average MIDI song file, three minutes in length and containing a dozen or more tracks will be about 20 kb in size.

The reason for this huge difference in size is that MIDI is, as discussed earlier, a language which *describes* what notes to play. The actual sounds themselves are generated by a connected MIDI device.

1.6 Audio Tracks

Dependent on your version of Logic, and the audio hardware installed on your system, you can play back up to 192 audio *tracks*. Each audio track has an associated audio channel strip in the Audio Mixer/Environment window. We’ll discuss the use of the mixer channels as we work through the Introduction Manual, but for now we’d just like to cover the relationship between “tracks” and “channels”.

Audio *tracks* and mixer *channels* are related.

Important!

You can not record or play back audio tracks unless a corresponding audio channel—also known as an audio “object”—is first created in the Environment window. Logic will automatically create a number of audio objects when first installed.

You can add and remove audio channels freely at any time, up to the capacity of your audio hardware and version of Logic. Adding extra channels means that you can then play back more audio tracks—provided that your computer and audio hardware are up to the task.

We will discuss the creation of audio objects/channels and tracks in the next chapter—The Ideal Workspace.

1.7 MIDI Tracks

Where audio tracks are said to have a corresponding “channel”, MIDI tracks have a corresponding “instrument” in the Environment.

This differentiation in terminology is very important to make a mental note of now. As we work through the Introduction Manual, you will discover many references to “instrument” and “channel”. We will clearly specify audio or MIDI channels throughout the Introduction Manual.

Important!

We will discuss the creation of MIDI instruments and other MIDI objects in the next chapter—The Ideal Workspace.

1.8 Logic Terminology

You’ve obviously encountered a few new terms at this stage, like *channels*, *objects*, the *Environment* and many more. This brief overview will provide you with some simple explanations before moving on to the mechanics of using Logic’s interface.

- **Object**—Logic is an “object-oriented” program, which means that it is “oriented” towards your interaction with graphical “objects”, in order to make use of them. A “sequence” or “audio region” could be considered an object, as could a graphical fader in the Environment window, or another graphical element of Logic’s interface.
- **Audio Region**—An “audio region” is an “object” which appears in the Arrange window. It is simply a pointer to an “audio file”, or a part of an audio file.
- **Audio File**—This is a computer file which is a digital recording of a sound. Please refer back to the *Audio* section, from page 19 onwards, if you need a refresher.
- **Sequence**—An “object” which contains MIDI data. This MIDI data can include note, program change, controller or other types of MIDI “events”. Please refer back to the *MIDI* section, from page 15 onwards, if you need a refresher.
- **Event**—refers to a single MIDI message. Technically, a “single” MIDI message such as a note event contains four messages, but in Logic you will deal with a single “event” onscreen. MIDI events can be displayed in a number of different ways by making use of several different editing windows available in Logic.




The individual editing windows will be discussed in far more detail as you work through the Introduction Manual, but here’s a quick rundown on the windows you’ll use on a day-to-day basis:

- **Arrange**—Logic’s primary working window. Here, you can record, arrange and mix MIDI and audio “objects”. MIDI objects are known as “sequences” and audio objects are known as “audio regions” in the Arrange window.
- **Event List**—This editor provides a detailed view of “events” and “objects”, allowing you to directly interact with, and manipulate them, in an alphanumerical (letters and numbers) list.
- **Matrix**—Note “events” are displayed as horizontal bars onscreen. You can directly interact with these events graphically.

- **Score**—Again, note “events” are displayed and edited graphically, but in the form of standard musical notation.
- **HyperEdit**—This is a grid-based graphical editor which allows you to “draw” in various types of MIDI events.
- **Track Mixer**—Provides control over volume and pan plus other parameters for your MIDI and audio hardware devices. Here, you interact with “objects” which look, and behave, like the faders on a mixing console.
- **Environment**—This is a graphical window which essentially allows you to set up the input and output routing of your MIDI and audio hardware by using icons which represent your audio and MIDI devices.

1.9 The Mouse

Basic Functions

Many functions performed with the mouse make use of “modifier” keys—, , and  in conjunction with the methods outlined below.

Clicking

Place the mouse pointer on the desired “object”—button, input field, MIDI note event, sequence, audio region or file etc.- and press (and release) the mouse button quickly.

Double-clicking

The same as clicking on an object, but you press the mouse button twice, in quick succession. You can set the appropriate time-span between clicks in your operating system’s Control Panels.

Grabbing or Click-holding

The same as clicking on an object, but you keep the mouse button held down.

Moving or Dragging (Drag 'n Drop)

Grab the object and move the mouse (with the mouse button depressed) to the desired position. You will generally release the mouse button to “drop” the object once the desired destination has been reached.

Scrolling

Throughout Logic, many menus and windows allow you to scroll horizontally or vertically. In most locations this is done with the mouse button depressed.



Mouse Input


Checkboxes

Checkboxes are square boxes which become “checked” when you click in them to activate an option (or function). Clicking in them a second time will remove the “check” and deactivate the option.

Pull-down (Flip) Menus

Pull-down menus (also known as Flip menus) open when you click and hold on certain input fields or buttons. You can make a selection within the menu by scrolling to, and highlighting, the desired item and releasing the button. If you wish to choose an item which is outside the visible section of the flip menu:

- Move the mouse over the top or bottom edge of the menu; the further you move it, the faster you will scroll through the menu.
- Hold down the  key as you do this. You can then release the mouse button and use the scroll bar to the right of the flip menu to scroll through it. When the desired entry is reached (indicated by the highlight), release the  key

 Many of Logic’s menus are “sticky”. This means that once the menu is opened, the mouse button can be released and the menu will



remain open until an option is selected or until you click outside the menu with the mouse.

Mouse as Slider

Almost all numerical parameters, including note values and lengths, can be adjusted by click-holding on the parameter value and moving the mouse up or down. If the parameter is comprised of several separate numbers (e.g. song position), you can adjust each individually.


Numerical Input

Double-clicking on a numerical parameter value opens a numerical input field. The previous value will be highlighted, allowing it to be overwritten with a new entry. You can also use the mouse to make a partial selection in an input field so that only the highlighted value is overwritten (e.g. song position).

As long as an input field is open, the computer's keyboard is limited to data input, and may not be used for Key Commands.

Important!

... by arithmetic

At any time, you can enter numbers by typing in an arithmetical operation, e.g. "+2" or "-5", which then simply changes the current value by that amount. Hit the  key to activate your choice and exit the parameter field. Alternately, you can click once on the window, anywhere outside the parameter area.

... as ASCII-symbols

You can also input numbers as ASCII symbols: Simply type a ` or " in front of the symbol, and the ASCII code will be input as a number. For example:

"! results in a value of 33

"a results in a value of 97

This function is particularly useful for entering text in SysEx strings.

Text Input

Text names are altered in the same fashion as described for numerical input, but the name field need only be clicked once to allow input.

Numbered Names


You can give any number of selected objects the same name. If the name ends in a number, the number will automatically be incremented by 1 for each subsequent object. This allows you to name all sequences on a single track quickly, while retaining a differentiation between them. The selection of multiple objects is discussed in the *Selection Techniques* section, from page 38 onwards.

Disabling automatic numbering

To disable automatic numbering, place a space after the number at the end of the name. All selected objects will then end in the same number.

Tools and the Toolbox

Logic allows recorded data to be handled graphically. This means that you don't need to perform editing operations via arcane command line or table entries. Rather, you can deal with your data by manipulating graphical "objects" which represent your notes, volume levels, pan positions etc. You do this by using "tools".

When editing objects graphically, you always have two tools available for immediate use, without needing to visit the Toolbox. One is already active, and the other is activated by holding down the  key.

You can change the currently active tool by clicking on the appropriate tool in the Toolbox. The mouse pointer will adopt the shape of the selected tool, enabling you to know what function is assigned to the mouse by simply looking at the mouse cursor. The Eraser is used for deleting, the Scissors for cutting and the Glue tool for merging objects.

Effective Range of the Tools

- Tools are only effective in the working area of the editing window in which they were selected. Individual tools can be defined for each open window.
- A tool basically affects the object you click on. If multiple objects are selected, the tool will operate on them all.

Opening the Toolbox at the Mouse Position

Use *Show Tools* (default: **[esc]**) to open a toolbox at the mouse position. This window will disappear as soon as:

- you choose a tool by clicking the mouse
- you choose a tool by pressing a numerical key
- you click anywhere outside the tool window or
- press any key.

Tip



Selecting Tools

To select a tool, click on it in the toolbox.

If a toolbox is opened at the mouse position (Key Command: *Show Tools*, Default: **[esc]**) you can also use a numerical key to choose a tool. Tools are numbered from the top left to the bottom right. Press the Show Tools key again to deselect a tool, switch to the pointer, and close the box.



Info Line

The Info Line replaces the local menus in the active window on Mac OS.

The Info Line provides useful feedback about the type of operation you are performing. During operations involving Arrange window objects, the Info Line will look similar to the following:

Move Objects	1	1	1	1	Pad	13	8	0	0	0
--------------	---	---	---	---	-----	----	---	---	---	---

From left to right, the Info Line displays: name of the operation, mouse (or Arrange window object) position, Arrange window object name, track number, and length of the Arrange window object.

During operations involving events, the Info Line looks something like this:

Move Objects	1	1	3	1	Note	1	F#3	80	1	0	0
--------------	---	---	---	---	------	---	-----	----	---	---	---

From left to right, the Info Line displays: operation, mouse (or event) position, event type, event MIDI channel, first data byte (i.e. the pitch for notes), second data byte (i.e. velocity for notes), and for notes: length of the note.


About the Tools

There are additional tools to those outlined below, which are found in specific editing windows. The following are the primary tools used in song construction and editing. The window-specific tools are discussed in the Introduction Manual and Reference manual, in conjunction with topics and examples covering their use.

Pointer

The Pointer is the default tool. The mouse cursor also takes on this shape outside the working area, when you are selecting from a menu or entering a value. Within the working (active) area, the Pointer is used for:



- selecting (by clicking on objects)
- moving (by click-holding and dragging)
- copying (by holding down the  key and dragging) and
- editing lengths (by click-holding the bottom right or left corner and dragging).

- click-holding and dragging anywhere on the window's background allows you to “rubber-band select” multiple objects.

Pencil

The Pencil is used to add new objects. You can also select, drag, and alter the length of objects with this tool.



Eraser

The Eraser deletes objects. This is done by clicking on them once. When you click on a selected object, all other currently selected objects are also deleted (as if you had used the **[B]** key).



Text Tool

The Text tool is used to name Arrange and Environment window objects or to add text to a musical score.



Scissors

The Scissors are used to split Arrange window objects, e.g. before copying or moving individual sections.



Glue Tool

The Glue tool is the opposite of the scissors: all selected objects are merged into a single object, which is given the name and track position of the first of the objects on the time axis.



Solo Tool

Click-holding with the Solo tool allows you to isolate and listen to selected objects. This function works during playback or when the sequencer is stopped. Soloed objects will be outlined in yellow.



Mute Tool

Clicking on an object with the Mute tool stops it from playing and places an asterisk in front of its name, to indicate that it is muted. The color of the object is also muted, so a bright purple will turn a shade of lilac, for example. You can unmute the object by clicking on it again with the tool. If multiple objects are selected, the mute tool will affect them all.



You may also wish to activate the **Muted Objects are textured** parameter in the **Options > Settings > Display Preferences**, to further highlight muted objects. This is particularly useful on gray (non-colored) objects.

Tip

Zoom Tool

The Zoom tool allows you to zoom in on a section by “rubberbanding” it, right up to the maximum possible window size. To revert to a non-zoomed view, click on the background of the active window with the Zoom tool.



Crossfade Tool

In the Arrange window, the crossfade tool allows you to simply click-hold and drag across the section where two audio regions meet. A crossfade will automatically be created between the regions.

Velocity Tool

In the Matrix and Score editors, you can use the “V” tool to change the velocity of notes. To do so, click-hold on the desired note(s) and scroll vertically. Moving up increases velocity, and down decreases velocity.



1.10 Window Functions

The basic functions of Logic’s edit windows are the same as those found in other Macintosh applications. The display options available in Logic’s windows, however, are far more extensive.

In Logic, you can open different combinations of edit windows (even several of the same type) and adjust each one individually. All open, and “linked” windows in a song are constantly updated. When linked, any alterations made in one window will immediately update the display of all other open windows. The various windows can also be set to follow the song position. We will discuss the relationship between edit windows at the beginning of the next chapter.

Working with Windows


Opening and closing Windows

All Logic edit windows can be opened via the **Windows** main menu. You may open as many copies of the same type of window as desired. The relevant Key Command, which allows you to open the window without using the mouse, is displayed behind each menu item. Read the *Key Commands* section, from page 46 onwards for further information on these keyboard shortcuts.

Each time you use the **Windows** menu, take a quick look at the Key Command for each edit window—that way you will soon memorize them. As a preferable option to visiting the **Windows** menu, simply use the Key Commands as indicated. If you develop the “habit” of using keyboard shortcuts rather than the mouse, you will find Logic much faster and more elegant to use.

Tip

You can close windows by clicking on the close symbol to the top left of the windows.

If you hold down the  key as you click, all open windows in the active song will be closed.

Setting Window Size

You can adjust window sizes by dragging the lower right-hand corner of the window, as with any window in the Finder.

Maximizing window size

The windows maximize button, found in the upper right corner of the window, toggles the window between its maximum size, and the size it was prior to clicking the button (**Windows > Zoom Window**).

Selecting the Working Area

Scroll Bars

The scroll bars are situated along the right and bottom edges of a window. They are visible when the working area exceeds the dimensions of the window on either the vertical or horizontal axis.



You can scroll through the working area by clicking the arrows found at either end of the scroll bars or by click-holding and dragging the scroll slider. Note that:

- the size of the scroll slider changes in relation to the overall length of the scroll bar
- the scroll bar's length corresponds to the overall size of the working area
- if the working area and visible area are of a similar size, the scroll slider will be longer
- the visible section changes as you move the scroll slider.

X/Y Element

The X/Y element is situated at the bottom left corner of the window. By click-holding and dragging it, you can move both horizontally and vertically on the currently displayed window section, as if you were dragging both scroll bars simultaneously.



Page Scrolling

Use the *Page Up*, *Down*, *Left* and *Right* Key Commands to scroll one page up, down, left or right.



The *Page Top*, *Bottom*, *Left most* and *Right most* Key Commands move the visible section of the working area to the top, bottom, left or right, as if you had grabbed one of the scroll bar sliders, and moved it to one of its extreme positions.



Zooming

The telescope-shaped zoom symbols in a window are used to zoom in and out on the working area display. Clicking the smaller side of the telescope symbol reduces the size of the objects in the display, allowing you to see more objects in the same space (zoom out). Clicking on the telescope's larger side increases the size of objects in the display (zoom in). In some windows, only one telescope is available, and is used for simultaneous horizontal and vertical zooming.



- While “zooming”, the top left *selected* object will be kept in the visible region, whenever possible.

Zooming Selectively

Zooming In on a Section of the Screen

To enlarge a section of the screen until it fills the whole window, use the Zoom tool to “rubber-band” the desired section. You can do this repeatedly until the required viewing size is attained.



Reverting to the Previous Zoom Setting

Click on the window's background with the Zoom tool. This will return the zoom to the previous setting. If you have used the Zoom tool multiple times, then each click on the background will take the zoom level back one step, until the original zoom setting for the window is reached.

Window Elements

Adjusting the Size of the Window Elements

If you move the mouse over the top left corner of the Arrange area, the mouse pointer turns into a crosshair. By dragging it, you can now adjust the size relationship of the Bar Ruler, Arrange area, Track List and Transport (if shown). You can also adjust the window elements in the Score and Matrix Editors using the same method.

Concealing/Revealing the Transport Functions

Use **View > Show Transport** to display or remove the transport panel from the top left corner of the Matrix or Arrange windows. The number of buttons and indicators shown is dependent on the amount of space available to the transport.

Concealing/Revealing the Parameters

The **View > Show Parameters** (*Hide/Show Parameters—Key Command H*) function allows you to display or hide the entire area to the left of the Arrange and other editor windows. This area normally contains the toolbox, sequence or object parameters. Hiding these parameters allows more space for the edit window itself.



Menus

Most functions are not found in the main menu bar, but appear as local menus. These local menus will update to offer functions that are relevant to the currently active editing window.

Key Commands


Many menu functions can be accessed via computer keyboard shortcut keys, or combinations of keys. The keys (or combinations) used are shown alongside the menu entries.

Please note that you may assign many functions to any desired key (or combination of keys) via the Key Commands window. Read the *Key Commands* section, from page 46 onwards for further information.

Menu Options with “...” in their Title

Three periods following a menu function, as shown: ..., indicates that the entry will open a dialog box, rather than directly perform a function.

Dialog Boxes


In Dialog boxes, you can hit the highlighted button by pressing the  key.



Window Types

You can open as many windows as desired, including several of the same type. Even though the contents of all windows are constantly updated, only one window has the status of being the “top”, or “active” window. This is the window which is in the foreground, when several windows overlap.

The active window can be recognized by its fully-shaded title bar. The main distinguishing characteristic of this window is that Key Commands only affect this window, and not any of the others.

 The “floating” Transport bar is a special type of window. It is always “on top” and cannot be obscured by another window.

Links between Windows

The two buttons to the top left of a window (shown here), determine the window’s relationship to the song position (Catch), or to other windows (Link).



Catch

The Catch function means that the visible section of a window follows the song position as the song plays.



If the button with the walking man on it is illuminated (i.e. if it is blue), the window's display will update to follow the song position as the song plays. If the button is not lit, the display does not update, even when the song position line scrolls beyond the right-hand side of the visible portion of the window.



To toggle this on/off, simply click on the button, or you can set up a Key Command for the *Catch Clock Position* function.

Tip

Automatic Catch Disabling

If you move the visible section manually, Catch is automatically switched off, which ensures that the selected song section doesn't disappear, as the display updates to follow the song position line.

Autocatch

The **Enable Catch when Sequencer starts (Options > Settings > Global Preferences...)** function always enables Catch mode whenever you press play or pause.

Link

Clicking on the Link button activates Link mode. This means that the window will show the contents of the selected object. Selecting a sequence in the Arrange window will update the display of the linked editor to show the contents of the selected sequence.



1.11 Selection Techniques


Whenever you wish to perform a function on one or more objects, you must first “select” the object(s). This applies to Arrange window objects—MIDI sequences and audio regions—and individual events (notes, controllers etc.). Selected objects are either highlighted, or will blink on and off (in the Score editor).

The selection status of an object applies to all windows. A specific object selected in one window will also be selected in all other open windows that display the same object. Changing the top window doesn't affect the selection. Ensure that you don't click on the edit window's background, as this will deselect everything. Click on the desired window's title bar should you wish to switch between open windows without canceling the selection.

Selecting Individual Objects


An individual object may be selected by clicking once on it, and deselected by clicking on the window's background, or by selecting another object.

Selecting Alphabetically

The  key selects the next object in alphabetical order. In the Arrange window, pressing any alphabetical key will select the first object with a name that begins with this letter, provided that no Key command is also assigned to this key.



Selecting Several Objects

To select several non-contiguous objects, hold down  as you click them. As you click on subsequent objects, the previous selections are retained. This also works with horizontal or rubber-band selection.



Horizontal Selection


To select all objects aligned horizontally on a track, click quickly on the track name in the Track List. Similarly, you can select all notes of a certain pitch in the Matrix editor by clicking the relevant key on the onscreen keyboard.

If in Cycle mode, track selection will only select events falling within the Cycle zone.



“Rubber-Banding”

To select adjacent objects, click on the window’s background and drag a “rubber band” over them. You will see an outline appear onscreen. All objects touched or enclosed by the rubber-band outline will be selected, and will be highlighted to indicate their selection status.

Toggling the Selection Status



When you make any selection (including by rubber-band or horizontal selection), while holding down the  key the selection status of the objects is reversed.



You can reverse the selection status of all objects by using **Edit > Toggle Selection**— . Useful, for example, if you wish to select all objects except for a few. In situations where dozens or hundreds of objects exist, it’s easier and faster to first select the “few” you wish to leave unaltered, and then choose **Toggle Selection**.





Selecting Following Objects

To select all objects which chronologically follow a selected one (or, if no object is currently selected, to select all objects after the current song position), choose **Edit > Select all following**— .







Selecting Objects within the Locators (Vertical Selection)

Edit > Select inside Locators— —selects all objects lying completely or partly within the locators.



Selecting Similar or Identical Objects

If you have selected an object, you can use the **Edit > Select > Select Similar Objects**— —function, to select all similar objects and the **Edit > Select > Select Equal Objects**— —function, to select all equal objects.



This table will assist you in defining “similar” or “equal”:

Object	Similar	Identical
Controller Event	Controller# equal, any data byte	Controller# and data byte (control value) equal
Note Event	Note equal, any octave	Note and octave equal

Selecting All Objects

To select all objects, use **Edit > Select All**—.



Deselecting All Objects

You can deselect all objects by clicking on the background, or by using the *Deselect All* Key Command.



1.12 Edit Operations

The **Edit** menus for Logic’s various windows all take the same form. The first item is **Undo**. Below this, you’ll find the typical clipboard functions (**Cut**, **Copy**, **Paste**), and at the bottom of each menu are the main selection commands.

Undo

Undo allows you to reverse the previous edit. In **Options > Settings > Global Preferences**, you can disable the warning message that normally appears when you activate Undo, by checking the **Disable safety alert for Undo box**.



The Key Command for Undo is .



The Clipboard



The clipboard is an area of memory into which you may cut or copy selected objects. These objects can then be pasted to a different position. The clipboard is independent of any particular song, which means that it can be used to exchange objects between songs.

Cut

All selected objects are removed from their current position and placed in the clipboard. The previous contents of the clipboard are overwritten in the process:  .





Copy

A copy of all selected objects is placed on the clipboard. The selected objects are also left in place. As with the Cut function, the previous contents of the clipboard are overwritten ( .



Paste

All objects from the clipboard are copied to the top window. The clipboard is not erased in the process ( .





The contents of the clipboard are added at the current song position (if they are events or Arrange window objects). The song position is incremented by the length of the pasted objects.

In the Arrange window, the contents of the clipboard are pasted to the selected track. If events are pasted in the Arrange window, either a new sequence is created for them, or the events are added to a selected sequence.

Any objects that previously existed remain unchanged.

Clear

Edit > Clear erases any selected objects. Clear has no effect on the clipboard and is functionally identical to pressing the   key.



1.13 General Functions of the Editors

Opening Editors

There is a flip menu in the **Options > Settings > Global Preferences** that allows the selection of the editor that will launch, when a sequence is double-clicked in the Arrange window. The flip menu options are: the Score, Event, Matrix or Hyper Editor.

Control Output via MIDI

Activating the MIDI Out button causes MIDI events to be sent when they are added, selected, or edited. This allows you to audibly monitor every edit, whether you are scrolling through the Event List (automatic selection) or lengthening or transposing a note.



Automatic Scroll Functions

... scrolling to the Song position

The walking man button activates the Catch function, which updates the window view to show the current song position.



... scrolling to the selected event

The *Scroll to Selection* Key Command automatically moves the window, so that the first of the currently-selected events is visible.



Setting Locators by Objects

The **Functions > Object > Set Locators by Objects** command allows you to set the locators in all Editors (and the Arrange) so that they encompass the currently-selected events. The Key Command can be found in the Key Commands window under **Global Commands**.



Copy MIDI Events

By selecting **Functions > Copy MIDI Events** you can move or copy all events which fall between the locator positions, to a different position. By default, this is the current song position. When this function is selected, a dialog window will open which displays several copy parameters, as discussed below.



Locators

The start and end points, in which events to be copied fall, must be defined. The most recently used Cycle Locator points are automatically shown in the *Copy Events* window.

First, set the Locators in the bar ruler or Transport window, and then open the *Copy Events* window.

Tip

Destination

The **Destination** defines the position where the copied events will be inserted. The **Destination** point is defined by the current song position, so choosing a **Destination** is as easy as moving the song position line. If preferred, you may change the position in the *Copy Events* window. The SPL will move to the newly selected position.

Number of Copies

Any number of copies can be generated. Logic copies the segments successively. This option is not available in Swap Mode.


Mode

Clicking on the **Mode** field activates a flip menu with a list of options. The Copy Mode determines how Logic will manage the source and destination data:

Mode	Result
Copy Merge	The copied data will be merged with any data at the destination position.
Copy Replace	The copied data replaces any data at the destination position.
Copy Insert	The copied data is placed at the destination position, and existing data is moved to a later position to accommodate the new data.
MoveMerge	Like Copy Merge, but the source data is moved, instead of copied.
Move Replace	Like Copy Replace, but the source data is moved, instead of copied.
Move Insert	Like Copy Insert, but the source data is moved, instead of copied.
Rotate	The source data is moved to the destination position. The destination data, as well as all data between the end of the source data and the destination position, will be shifted towards the source position.
Direct Swap	Source and destination data exchange positions.
Remove	The source data is deleted.

Deleting Events

These basic techniques are the same as for deleting sequences:

- the  (delete) key deletes all selected events,
- the Eraser also deletes all selected events, and any events that you click with it (whether previously selected or not).



Display Functions

The **View > Show Parameters** (*Hide/Show Parameters—Key Command H*) function hides/shows the parameter boxes to the left of the window(s), allowing an enlarged working area.



1.14 Key Commands

You can activate most of Logic's functions via Key Commands. A Key Command is a computer keyboard shortcut for a function or task in Logic. A number of functions are only available as Key Commands. The Key Commands window is used for the assignment of Key Commands to your computer's keyboard. The use of Key Commands allows you to customize Logic to suit your own working style, and will speed up your use of the program.

Your personal Key Commands are stored (along with settings made in the Preferences pages) in a file called:

- “Logic 5 Preferences” in your Macintosh System folder (in the *Preferences* folder, to be precise).









You should:



- make a backup of this file elsewhere on your hard disk;
- make a floppy disk, ZIP or CD backup of it should you need to use Logic on another computer.

When you install updates for your version of Logic, your personal Key Commands will not be overwritten.



Special Keys


Some keys have special functions:

- The modifier keys , , , and  can only be used in conjunction with other keys. Given the differences in some Macintosh keyboards, we have included the following:
The  key = Shift.
The  key = Option.
The  key = the Command key.
- The  key has the fixed “delete selected objects” function. It can only be assigned to another function in conjunction with the modifier keys.

- The  and  keys increase or decrease any selected parameter value in single units. However, they *can* be assigned different functions which overwrite this default behavior.

Key Commands Window

The Key Commands window can be opened by selecting **Options > Settings > Key Commands** or by pressing  .








All Key Commands are listed to the right of the Key Commands window. They are grouped in the following categories:

- Global commands
- Functions affecting all windows (Various windows)
- Functions affecting the Arrange and all other Editor windows (Arrange & Various sequence Editors)
- Functions for the Arrange window specifically (Arrange)
- Functions for the Score Editor (Score window)
- Functions for the Event List Editor (Event window)
- Functions for the Sample Editor (Sample Edit Window)
- Functions for the EXS24 Instrument Editor (EXS24 Instrument Editor)
- Functions for the Note Step Input (Keyboard Input).


An asterisk or dot which precedes the function description indicates that the function is *only* available as a Key Command. To the left you can see the currently assigned key/key combination.

Assigning a Function to a Key

- Click on the **Learn Key** button.
- Select the desired function in the list by clicking once on it with the mouse.
- Press the desired key on your computer keyboard, plus the modifier keys: , ,  and .
- To create further Key Commands, repeat steps 2 and 3.
- Deactivate the **Learn Key!**



Deleting Key Command Assignments

- Click on the **Learn Key**.
- Use the mouse to select the function with a key assignment that you wish to delete.
- Press .
- To erase more assignments, repeat the second and third steps.
- Deactivate the **Learn Key** button.




Checking the Function of a Key

Deactivate the **Learn Key**, and press the Key Command (or combination of keys) that you want to check. The associated function will be highlighted, and displayed in the middle of the window.


Filtering the Display


You can use the **Hide Used** and **Hide Unused** buttons to hide all used, or unused, Key Commands. All other Key Commands window functions remain available for your use.



Finding Key Commands

Due to the large number of possible Key Commands, it can sometimes be difficult to find a particular function. To aid in this regard, Logic offers a **Find** function, which allows a search for a specific Key Command by typing in its function name (or a part thereof) or by entering a character string, i.e. the Key Command itself.

Simply click in the white space to the right of the **Find:** button and enter the string of characters (or function) you're searching for. The window will update to display all Key Commands containing the character string (plus the selected command, even if it doesn't contain that string) when the **Find** button is clicked or the  key is pressed.



The **Find:** button switches Find mode on and off. The button is automatically activated if a string of characters is entered in the text field.

The Key Commands window remains active, even in Find mode; you don't need to leave this mode to continue making assignments.

The Find function is not case-sensitive and makes no distinction between upper and lower case characters.

The **Hide Unused** and **Hide Used** buttons work in combination with Find. This means that you must switch off both in order to see *all* commands that fit the search criteria, regardless of the commands' current assignment.

1.15 Controlling Windows—Screensets

Every song created in Logic can have up to 90 “Screensets”. Screensets are window combinations which can be customized by you and stored to a specific numeric key/combination of keys on your computer keyboard. Each Screenset remembers

the type of edit or Arrange window/s opened plus size, position and zoom settings. This facility accelerates your workflow massively and allows you to tailor Logic to fit your needs and tastes.

To Set up a Screenset

- Press any of the numeric keys above your computer keyboard (you can also use the numeric keypad, if available).
- Open the desired windows by selecting them from the **Windows** menu, or by using the appropriate Key Commands.
- Resize, zoom and reposition your selected windows to meet your needs.
- Press the numeric key again.

This will only work for keys/Screensets 1 to 9.

Tip



To Set up More than Nine Screensets

- Press the **ctrl** + numeric keys.

You can *not* use the number “0” for any of your Screenset combinations. The reason is that number 0 is assigned for the Transport Bar **Stop** function, using the computer’s keyboard (or **Play** on Mac OS).

Tip

To Lock Screensets

- To ensure that your Screensets remain as you intended, you should always lock your Screensets by pressing  .



1.16 Song Administration

All events, other objects and settings (apart from the Preferences and Key Commands) are components of a song. Songs are handled in the **File** menu.

New Song

When you first launch Logic, it opens a default song. This song can be customized to match your needs and tastes for use in future projects. Once you have learned how to set up your own “default song”, by following this Introduction Manual, you should save it in the Logic program folder, and name it “Autoload”.

Autoload Song

If a song called “Autoload” exists in the Logic folder, it will automatically be loaded when Logic is launched. We will discuss the creation of an Autoload song in the next chapter. When you’re ready to start work on a new song, simply save the Autoload under a new name using **File > Save as...** and begin.




Creating a New Song

If you select **File > New**, Logic checks to see if an “Autoload” song is available and opens it automatically if found. If not, a new default song is created.



Opening the Default Song

If you hold down the  key while selecting **File > New**, a new default song called “Untitled” will be opened.



Loading a Song

File > Open will launch the standard file selection dialog for your operating system. Simply browse to the required song file.



Checking/Repairing Songs

If you double-click on the Transport Bar's free events display, the memory will be re configured. At the same time, the current song will be checked for any signs of damage, structural problems and unused blocks.

If any unused blocks are found—which normally shouldn't happen—you will be able to remove these, and repair the song.

Saving Songs

When you select **File > Save** the current song will be saved with its current name intact.



If you don't wish to overwrite the most recent version of this song saved under this name (which is what will happen if you use the **File > Save**, command, use **File > Save As...** Here, you can enter a new name for the song (and select a new directory or even create a new folder). The next time the straight **Save** command is used, the new file name and path will be used.




Closing a Song

File > Close closes the currently active song. If you have made any changes since the song was last saved, Logic will ask if the song should be re-saved before closing, to preserve any changes you may have made.



Quitting the Program...

Choose **File > Quit** to exit the program. If you have not saved any changes made to the open song file/s, you will be asked if you wish to do so before quitting (press  to save).



1.17 The Transport Bar


The Transport Bar is used to “transport” you to different points in your song. The buttons—from left to right on the top row of the left hand side of the Transport are: Record, Pause, Play, Stop, Rewind and Fast Forward. These work as per those on a tape deck. The record button, to the top left, is used for recording both MIDI and audio data on any currently *armed* track, selected in the Track List. The cycle, drop and other buttons on the lower row will be explained as we work through the Introduction Manual.








- The SMPTE/Bar Position area indicates the current bar number occupied by the Song Position Line. In the figure above, the display shows 1 1 1 1, which means: first bar, first beat, first 16th and first clock pulse. The time position, 00:00:00 etc. means—0 hours, 0 minutes, 0 seconds, 0 milli-seconds/frames a. s. o.
- The lower two sets of numbers, from top to bottom, are the left and right Locators, which are used for setting cycle region points, which will be discussed shortly.
- The Tempo display indicates the tempo accurate to 1/10,000 of a Beat Per Minute.
- Beneath the tempo, the maximum number of MIDI events that it would be possible to record on this particular computer is indicated.
- The /16 below the Time Signature of 4/ 4 indicates the format for note and bar display, so that any edits you may perform on your MIDI or audio data can be carried out with more precision. The /16 refers to the number of divisions in the bar. Click and hold your mouse button, and drag up or down to change this value.

- The MIDI Activity display shows all MIDI input and output and also serves as a “Panic” button. If you have hung notes you can click once in the MIDI Activity Window to send a MIDI reset message, or double-click to send a Full Panic Reset which systematically works through all MIDI channels and ports and resets all connected MIDI devices. This guarantees absolute silence.
- The Song End box displays the bar number at which the song will end and sets a maximum song length. By default this is set to 201 bars.
- Clicking on the downwards pointing arrow beside the Song End box will open a menu of Transport Bar display options, which will allow you to customize the appearance of the Transport bar to meet your requirements. We suggest that you select “Legend” which will turn on the function titles, as shown in the image above, at least while learning Logic.

Transport Key Commands

By default, there are several Key Commands assigned to the transport functions. They are assigned to the numeric keypad of your computer keyboard.  must be activated for them to function using the numeric keypad. See the following chart for these commands, and try to remember and use them while working through the Introduction Manual.

Key Command	Function
 *	Record
 /ins	Play /Play from Locator if set
 , /del	Pause Toggle
 ↵	Stop
 pressed twice	Return to Zero

Simple Science...

That's about as technical as this Introduction Manual gets. We don't want to blind you with science, we just want to help you get up and running with Logic.

Where necessary, we will offer tips and explanations of features and functions, but most of the time you will learn by doing. Please refer back to this chapter if you forget how to use any of the tools, menus or other functions. If, at any stage, you would like to get detailed technical or other information on any feature or term discussed, you can use the Reference Manual supplied with your version of Logic.

Take as much time as you need to complete each task, and have fun experimenting with the supplied song files.

Your Emagic Team

Chapter 2

The Ideal Workspace

By following the exercises, examples and steps here with your own MIDI and audio hardware, you will create your own customized workspace.

Once this groundwork has been done once, using the Environment window, you will have a default working song file that can be used as a basis for all of your future projects. This will be known as your “Autoload” song.

Furthermore, you will learn how Logic communicates with audio and MIDI hardware and will start making your first experimental musical steps.

Before we get to the Environment window, we’d like to briefly cover some conceptual information. This will aid you in understanding the structure of the program, and the relationships between windows in Logic.

2.1 3 Dimensional Software

Logic has a structure unlike most software you may have used. Where Logic is different, is that it features several “levels” to its architecture. If you compare this to other Mac OS software, you can open several documents or “windows”, in which you can view and edit content. But there is no relationship between these windows. In Logic, all windows are linked and interact with each other.

Let’s take a look at Logic’s different windows and levels:

- The Arrange window is where you construct your arrangements and songs. In the Arrange window you deal with *folders* and with *MIDI sequences* or *audio regions*. *Folders* can contain *MIDI sequences* or *audio regions* or other *folders*. The *MIDI sequences* contain *MIDI events*. You do not deal with *MIDI events* or *audio files* directly. You do this in the different Editors.
- In the Editors, folders, MIDI sequences and audio regions can be opened to look at, and directly manipulate, the raw MIDI data—notes, controllers, sysex messages etc.—and the underlying audio *file* on which the *audio region* is based. The editors allow you to go into the depth of your composition—from the top level of the Arrange to the folders to the atomic level of notes and audio files. Let's take a closer look at two of the editors.
- The Score editor allows you to switch between viewing a score part for a single track, an individual sequence, a group of tracks, and the entire song. This allows you to define what you would like to see onscreen and what part(s) you would like to print—without changing the MIDI data.
- Similarly, the Matrix editor allows you to simultaneously view the contents of a single sequence, all sequences on a track, or all sequences in a song, or song section. Viewing the contents of multiple sequences allows you to quickly see, and change, overlapping notes, velocities and more on multiple MIDI channels.
- Finally, there is the Environment, in which the Logic sequencer is connected to its MIDI and audio environment. The Environment can be divided into layers improved overview and easy access to your instruments. For example, you would normally have an Environment layer for your JV1080, another layer for your Nord Lead, another for your Virus, and another for your audio hardware.

These “link” buttons (chain symbol) are found to the top left of all of Logic’s windows. Their function is to keep the various windows “linked”, regardless of which *level* in the song architecture you happen to be working on—Arrange, Edit etc. You will learn more about the practical uses of these buttons—and the walking man icon found alongside these buttons—as you work through the Introduction Manual.



As you work with Logic, you’ll see the interaction between windows, and will learn the practical use of the levels and layers we’ve discussed. You will find that this method allows each window to perform a particular task efficiently. Key to Logic’s operation, and truly unique in the music software world, is the Environment.

2.2 The Environment Concept

Logic’s Environment window—accessible from the **Windows** menu—is Logic’s “brain”. Its primary purpose is to get MIDI and audio information into, and out of, Logic.


The Environment has a direct relationship to the Arrange window’s Track List: Each track has a destination, and this destination is an object in the Environment.

Important!

This is illustrated by the following diagram.

Chapter 2

The Ideal Workspace



The Arrange window Track List is shown to the left, with Track 12—Grand Piano selected. This track corresponds to MIDI channel 1 of the GM Device shown in the Environment to the right. Note that the number 1 button in the GM Device graphic is depressed. If Track 13, the Fingered Bass were selected, the Environment window would update to reflect this selection, and button 2 would be depressed in the GM Device. The automatic updating of the GM Device in the Environment window is due to the “linking” discussed earlier in this, and the first chapter.

2.3 The Data Flow

The Environment allows you to set up an onscreen “flowchart” which represents the functions and facilities of your connected MIDI equipment. On a basic level, you can simply define your “instruments” onscreen and route them to a MIDI port.

Important!

If you’re more adventurous, you can incorporate additional onscreen tools, such as arpeggiators, MIDI delay lines and more to your Environment. These additional tools, plus your onscreen “instruments” are collectively known as “objects” in the Environment. The Environment can even be used to create extremely flexible *real-time* MIDI data processing “machines”, including step sequencers, rhythm generators and more.


The key word and concept to keep in mind when dealing with the Environment is “flowchart”, no matter how simple or complex your Environment is, or becomes. The Environment allows you to clearly define how you want your MIDI data flow to be sent *to* and *from* your physical MIDI devices.

But the Environment does not stop with MIDI: You can also set up audio “objects” for your individual audio output, input, audio instrument, bus and master fader channels. The creation of a number of these audio objects, plus the routing of signals between them is *automatically* taken care of by the Logic installation procedure. You don’t need to set up anything before making use of the audio functionality of Logic.

Logic also allows the interaction of MIDI and specific audio objects in the Environment, which we’ll discuss later.

Getting Started

As you’re probably familiar with audio mixers, we thought it would be helpful to discuss the flow of audio signals as a point of comparison to the data flow in the Environment. Take a look at the following image.




As indicated by the arrows, audio signals run *out* of the synthesizers to the left and run *in* to the mixer in the center.

Signals run *in* and *out* of the mixer into/from the effects unit to the top right. This is often called an “effect loop” and is used to route the signals of the three synthesizers (as a group or individually) *in* to the effects unit (via the mixer’s *effect send*). After being processed by the effects unit, they will be sent back *in* to the mixer (via the mixer’s *send return*).

MIDI signal flow is no different, in concept at least, to the audio example above. It must be sent *out* of one device and *in* to the next device in a “chain”, just as with audio. Let us show you what we mean, and please give this a try.

- Launch Logic, if it isn’t already running by clicking on the Logic icon in your Logic program folder.
- From the **Windows** menu, click hold and scroll down to the Environment listing or use the **⌘** **8** Key Command. This will launch the Environment window.
- In the Environment, you’ll see the words “MIDI Instr.” on the left-hand side of the screen in the Layer flip menu (in the diagram it is shown as “(unnamed)”).
- Click-hold in this box and in the flip menu which opens, select **Create**. This will display a blank Environment *layer*.
- Click on the **New** menu and select **Physical Input** from the listing. Release the mouse button and a new physical input icon will be generated onscreen. (Yours may look different to that shown below as this is dependent on the type of interface used and platform).
- Click on the **New** menu and select **Arpeggiator**.
- Click on the **New** menu and select **Instrument**. You will now have three icons onscreen.



- Connect the cables as shown, ensuring that you cable from the **Sum** output of the Physical Input object.


- To create a cable, click and hold on the small triangle found at the top right of each icon and drag the mouse/cable (which will appear onscreen automatically) *in* to the target icon. You will know that the connection has been made when the target icon turns white. Once you've made the connection, release the mouse button.

If no triangles appear to the top right of your icons, click-hold on the **View** menu, and select the Cables entry. If you still have problems, select **View > Protect Cabling and Positions**.


Tip



- Click once on the Arpeggio object and, in the parameters box to the left of the screen, change the settings to match the following: **Direction—UpD2, Res—1/16, Length—1/32, Octaves—3**.
- Route the “Instrument” object to a MIDI *out* port that is active. You'll find this on the left of the screen in the parameters- as shown in the diagram below. Click and hold in the space between **Icon** and **Cha**, and select an available MIDI port from the flip menu. Once again, the appearance may be slightly different on your machine, dependent on the MIDI interface used and platform.



- Close the Environment window.
- Select the “Instrument” MIDI track in the Arrange Window by click-holding on any of the instrument *names* in the Track List. This will open a hierarchical menu as shown below.



Take a moment or two to scroll through the hierarchical menu. You will notice that the Instrument and Arpeggiator objects you created in the Environment also appear in this list—under the “unnamed” menu entry. This is a key point to understand. All objects you create—on *any layer* in the Environment: in this case the “unnamed” layer—will be available for selection and use in this hierarchical menu, and therefore in the Track List. In other words, the two are connected, and without objects in the Environment, the Track List will be full of “null” (No Output) objects.

Important!

You can prevent objects from appearing in the list by unchecking the **Icon** checkbox in the object’s parameter box in the Environment.

Tip

Another point to consider when selecting an output object—i.e. an Instrument—in the Track List, is the underlying routing of the Instrument within the Environment. If you select an Instrument on a track that has an arpeggiator routed *in* to it, for example, then all MIDI data on the track will be sent via the Instrument. If, on the other hand, the arpeggiator object was selected on a track, the data recorded on the track would be sent via the arpeggiator and fed, in turn, to the connected Instrument. This would result in the arpeggiation of the data.

Important!

Back to the example. This routing does nothing exciting until you hit the **Play** button on the Transport Bar and hold down a chord on your keyboard. Try it!



While doing so, we ask that you pay attention to the top right-hand field of the Transport Bar. This is the MIDI activity indicator which displays MIDI input and output. Once you've had a little fun, press the **Stop** button on the Transport Bar.



This is one of thousands of possible routings, but is a simple example of how the *signal flow* works.

Expanding this Example


Open the Environment layer you just created by double-clicking on the “Instrument” track in the Arrange window’s Track List. This will automatically launch the Environment window, and will select the layer and Instrument object itself. As you can see, the signal is routed from the Physical Input object directly *in* to the Arpeggiator object.

Tip

In Logic’s Environment, the *Physical Input* object is actually the equivalent of your real-world hardware MIDI In port(s). Click on the **New** menu, and slowly scroll through the various options. You will find a **Sequencer Input** object amongst the items listed. The *Sequencer Input* object that appears onscreen is actually the software input for Logic (the “door” in to the program, if you like)

Important!

- Connect your cables as shown.



- To disconnect the existing cables from the previous example, simply click on the *cables* and drag them to the new destination.
- To completely disconnect the cable connection between objects, simply click on the cable and drag it back on to the source—i.e. the icon it’s routed *from*.
- Once done, close the Environment Window.

Tip

- Now, if you press the **Play** button on the Transport and play a chord on your keyboard, it works just as it did before with one exception—the MIDI In on the Transport works.
- Once you’ve experimented a little with this, press **Stop** on the Transport.
- If you press the **Record** button on the Transport and play a chord, your arpeggiated data will be recorded. Give it a try, and note that as the recording takes place, a new sequence will be created in the Arrange window and displayed as a horizontal rectangle.
- Once you’re done with the recording of your arpeggio, press **Stop** on the Transport Bar.



Sit back and consider this for a moment, and take a look at the signal flow. In both examples, the data was routed from the actual MIDI port—i.e. the Physical Input object—into the Arpeggiator object, where it was processed.

Please Note: The only way to *record* MIDI data into Logic is via the Sequencer Input object. As shown in the first example, it’s possible to process MIDI data via the Environment without Logic “seeing” any MIDI input.

Important!

As a scenario where the ability to process MIDI data before it enters Logic (via the Sequencer Input object) may be practical, consider this: You have a basic MIDI keyboard that can only transmit on one channel at a time—e.g. a DX 7—but want to split/layer it in order to access and control multiple channels of a connected sound module simultaneously. In this scenario, you could set up your keyboard’s “phantom” controller functions in the Environment before the Sequencer Input object. Everything subsequently performed would be processed—i.e. split/layered/transposed etc.- prior to being recorded and would sound and work in the desired fashion.


It is also possible to set up similar functionality after the Sequencer Input object, although the routing would be very different. Some things, however, are difficult (if not impossible) as post Sequencer Input processes and vice-versa. As a rule, the arpeggiator would generally be used post (after) the Sequencer

Tip

Input, and would normally be routed directly *in* to an Instrument. In our example, all MIDI note data entering Logic would be arpeggiated, which wouldn't be great for many (or any) styles of music.

Parallel Processes


It's possible to route the MIDI signal through multiple processes in parallel, much like you would in a multi-effects processor.



The diagram shows a parallel routing scheme, post the Sequencer.

If you follow the flow of the signal in the diagram, you'll see a standard recording setup—the Physical Input runs into the Sequencer Input object, several other objects are connected independently.

Not quite as standard in the example shown above: Any MIDI note input played or recorded on the “Test In” Instrument track—selected in the Arrange window's Track List—will be routed through the Arpeggio, Delay Line and Chord Memorizer objects. All processing done by these objects will be routed to the “Test Out” object and will only affect its MIDI port/channel.



The diagram shows a slightly modified parallel routing scheme, post the *Sequencer*.

If you slightly modified this example, it would also be possible to route the data from each of the *Arpeggio*, *Delay Line* and *Chord Memorizer* objects to separate *Instrument* objects—e.g. “Test Out” 1, 2 and 3. This would mean that the data routed from the “Test In” track could be sent via the *Arpeggiator* to a synth “pluck” sound, the *Delay Line* to a bass sound, and the *Chord Memorizer* to a synth pad, for example.

As you can see, there is no cable between the *Sequencer Input* object and the “Test In” *Instrument* object. You may be wondering what happens to the MIDI data if the signal flow chain is “cut”, as it appears to be, between the *Sequencer Input* and the *Instrument* object. Here’s what happens:

Logic sees all MIDI data arriving at the *Sequencer Input*. The program routes any incoming data, in realtime, to the track you have selected in the Arrange. As the “Test In” *Instrument* object is selected as the track destination, the signal flow is not interrupted.

Important!

Once MIDI data has been *recorded* into Logic via the *Sequencer Input*, it will be stored within a MIDI sequence. The data within this sequence can then be directed to virtually any *Environment* object, via the track’s destination.

A Quick Recap

So far, we have covered some key Environment concepts, which are condensed as follows:

- The Environment's primary purpose is to get data into and out of Logic.
- The Environment represents physical MIDI devices and some of their functions via onscreen icons.
- The Environment contains additional processing tools, which can alter MIDI data in real-time.
- The Physical Input object represents your MIDI interface's INPUT ports.
- The Sequencer Input object is used to (and is the only way you can) *route* MIDI data into Logic.
- Once data has entered Logic via the Sequencer Input port, the program can redirect this data to almost any object that exists in the Environment.
- All objects you create—on any layer in the Environment—will be available for use as track destinations in the Arrange window's Track List. MIDI data, stored as sequences in the Arrange window, can thus be routed to any port, channel, instrument or to/from another object.
- Some objects, such as Instrument objects, can be routed to a MIDI output port with no need for any cabling.

As shown in these exercises, the main thing you need to do when in the Environment is to follow the signal flow. Think carefully about what you want to happen to your data, plus when and where in the signal path you want it to happen. It really is that simple!

2.4 Your First Environment

And now, we'd love to help you to set up your own Environment. This will form the basis of your future work with Logic, as the song you will create—your own “Autoload”—will be saved as a template for your future projects.

Given the endless variety of MIDI devices available, it's obviously impossible for us to cover every one of them here in detail. Logic offers a number of *universal* objects, which can be used—and customized—to represent your physical MIDI devices.

We will cover the *basic* set up of hardware with the goal of getting MIDI data in and out of your Logic system. We will do this by describing several devices and functions, and their equivalent object(s) in the Environment.

This information can be adapted to the devices you have in your studio. If you have multiple MIDI devices of a particular type—i.e. several multi-timbral synthesizers, 2 or 3 effects units, a couple of drum machines, etc.—simply repeat the setup procedure for each.

In the *Quick Environment Setup* section, from page 75 onwards, we will show you how to use the “Various Multis” song file that was installed in your Logic program folder. This song file contains pre-built Instrument objects for over 200 different MIDI devices. If all devices in your studio are contained in this song, set up of your Autoload song will take around five or ten minutes. If one or more of your devices is not contained in the “Various Multis” song, the other information contained in the *Manual Instrument Setup* section, from page 77 onwards, will aid you in setting up and customizing your Autoload.

If you own the full version of SoundDiver, please refer to the *SoundDiver* chapter, from page 212.

Should you wish to further enhance your Environment, after reading through this section, we would suggest to take your time. This will give you the time to read the Environment chapter in the reference manual, and time to learn how *you* want to use Logic, which will place you in a better position to then customize the program to meet your needs.

Once you have created a basic setup for your MIDI devices, you may wish to skip ahead to the *Using Logic* chapter, from page 113 onwards. You can always return to this chapter at a later stage, should you wish to customize, or add to, your Auto-load song.

Instrument Objects

As you've learned, if there are no *Instrument* objects in the Environment, the program has no idea of how and where to route MIDI data. To this end, you must inform Logic about the MIDI equipment in your studio. This is accomplished by the insertion of appropriate Instrument objects, namely the *Instrument*, *Mapped* or *Multi Instruments*. These *Instruments* will directly reflect the type, and number, of real-world MIDI instruments, effects units and channels of each device in your MIDI rig. Although the term *Instrument* is used, these objects can represent any MIDI-controllable device, be it a MIDI mixer, synth, lighting unit or whatever.

Important!

The Instrument Object

The Instrument object is designed for devices that operate on a single MIDI channel. This makes it the ideal choice for effects units, older synthesizers that operate on a single channel, electric pianos and some mixing devices.



The Multi Instrument Object

This object is designed for devices that operate on multiple MIDI channels simultaneously—i.e. multi-timbral synths. It is ideal for most modern synthesizers, and is the most commonly used Instrument object type.



The Mapped Instrument Object

Is suitable for devices such as drum machines or synthesizers that provide multiple sounds on one MIDI channel: Most modern multi-timbral synthesizers feature a “Drum” channel—usually channel 10. Where this is different to the other Instrument object types is that each sound, within the channel, is assigned to a different MIDI note number—i.e. a key on your keyboard.



Some Preparation

Before you begin the *Construction Time* section, from page 73 onwards, take a few minutes to look around your studio and jot down a list of all of your MIDI gear on a piece of paper. As you’re doing so, use the following chart as a guide.


- The *No. Channels* column indicates the number of channels that the device is capable of simultaneously producing sounds on—i.e. its multi timbral use.
- The Drum entries in the *No. Channels* column indicates that the device features a “drum” mode.
- The *Interface Name* Column indicates the MIDI interface the device is connected to.
- The *MIDI In/Out Port* columns indicate the physical port number on your MIDI interface that the device is connected to.
- The *Object Type* column indicates the type of Instrument object which should be used. Some entries use multiple Instrument types. MI = Multi Instrument, MP = Mapped Instrument, I = Instrument:

Device Name	No. Channels	Interface Name	MIDI In Port	MIDI Out Port	Object Type
JV1080	15- 1Drum	Unitor 8	1	1	MI/MP
K5000	4	Unitor 8	2	2	MI
MRRack	15- 1Drum	Unitor 8	3	3	MI/MP
Nord Lead	4	Unitor 8	4	4	MI
MicroWav	8	Unitor 8	5	5	MI
E4	16	Unitor 8	6	6	MI
S3000	16	Unitor 8	7	7	MI
O3D	1	Unitor 8	8	8	I
DM Pro	1Drum	MT 4	1	1	MP
M5000	1	MT 4	2	2	I

Using the chart above as an example, you can see that all of the devices routed to the Unitor 8 interface use a Multi Instrument object, except for the O3D mixer. The devices routed to the MT4 interface use a Mapped Instrument and Instrument object, respectively. Some of the devices—JV1080 and MR Rack—use a combination of Instrument objects, namely a Multi Instrument *and* a Mapped Instrument.

2.5 Construction Time

This section covers the creation of a number of different Instrument object types, applicable to your studio setup. Follow the steps outlined for each *type* of Instrument, referring to the studio gear list that you just wrote down. Where necessary, repeat the steps if you have several instruments of the same “type”—i.e. several multi-timbral synths.

Don’t forget the **Undo** function discussed in the first chapter, if you make a mistake in the Environment window. If you create the wrong type of object, you can highlight it by selecting it with a mouse click, and can delete it by pressing the  key.

Tip


Plain Vanilla Settings

Before starting, you will need to create a “plain vanilla” song file, i.e. a song with *no* MIDI Environment objects. This provides a uniform starting point.

Note that if you only own a single GM device (including internal sound cards), then Logic is ready to use, and will require no changes to the Environment. Save the default song as “Autoload” in the main Logic program folder, by selecting **File > Save As...** and typing in the name. But remember: You will learn more by following our “Vanilla” tour.


Tip

Creating a “Vanilla” song:

- Create a new Song by selecting **New** from Logic’s File menu.
- Open an Environment window by selecting **Windows > Open Environment**, or by using the Key Command.
- Select the “MIDI Instr.” Layer from the Layers flip menu.
- Select all objects on the layer by pressing  **A**.
- You may also make use of the **Options > Layer > Delete** function to completely delete the layer which contains objects you do not require. You can freely create new layers at a later stage by using the **Options > Layer > Insert** function. Should the layer contain any objects, the following warning will be displayed. Clicking **Delete** will remove the layer.



Tip



- Repeat these steps for all layers except the Click and Ports, Audio, and All Objects layers.
- Once all unnecessary objects (or layers) have been deleted, save the song as “Vanilla” in the main Logic program folder, by selecting **File > Save As...** and typing in the name.

Quick Environment Setup

You will probably find that at many, if not all, of your MIDI devices are contained in the “Various Multis” song file. Should you find that there are some devices which are not contained in the Various Multis song, please read the *Manual Instrument Setup* section, from page 77 onwards, to complete your studio setup. That section also contains information on customizations which you can make to your Instruments. These may be of benefit when using Logic creatively, so it’s recommended reading.

The Various Multis Song

The “Various Multis” song contains pre-configured Multi Instruments for over 200 devices. They are organized by manufacturer on separate layers.

Refer to your studio gear list and follow these steps.

- Open your “Vanilla” song file
- Open an Environment window by selecting **Windows > Open Environment**, or use the Key Command.
- Close all other open windows, leaving only the Environment open.
- Select the desired layer—Instruments, for example—via the layer flip menu to the left of the Environment window.
- If you made use of the **Options > Layer > Delete** function when creating your “Vanilla” song, select **Options > Layer > Insert**. Once created, browse to the newly created Environment layer.
- Select **File > Open**. You will be prompted by a dialog box asking if you wish to “Close current songs before opening new song?”. Click on the **Don’t Close** button.
- In the ensuing file selection window, browse to the folder which contains the “Various Multis” song file, which will launch the song file.
- Once open, you will see the Environment window, and a text window, which provides text instructions for use of the song.



- Select the manufacturer of the MIDI device you're looking for by click-holding on the Layer menu in the column to the left of the Environment, and scrolling to the appropriate manufacturer name.
- Select the appropriate device by clicking once on it.
- Select the **Edit > Copy** menu option.
- Go to the **Windows** menu, and select the "Vanilla" song. This entry is found towards the bottom of the menu.
- Ensure that the desired layer of the "Vanilla" song is visible via the Layer flip menu.
- Select the **Edit > Paste** menu option.
- In the parameters box to the left, select the appropriate MIDI interface/port you wish to route the imported Instrument to.
- Within any Multi Instrument, activate the appropriate number of channels, by clicking on each numbered square in the grid. Refer to your list while doing this to ensure that you only activate as many channels as necessary—i.e. as many channels as your MIDI device is capable of playing simultaneously.
- Repeat for each device.
- Once all objects have been added, save the song as "Autoload" in the main Logic program folder, by selecting **File > Save As...** and typing in the name.


One Layer or More?

Multi Instruments—either copied or manually created—can be placed on their own layers or on a single layer. The choice is yours.

Multi Instrument objects will create their own hierarchical menu listing in the Arrange window Track List. This list displays as many channels as you have activated within the Multi Instrument.

As this chapter of the Introduction Manual is aimed at setting up your Environment as quickly as possible, we would suggest that all Multi Instruments be copied (or created) on the "Instruments" layer of the Vanilla/Autoload song.

If, at a later stage, you decide that you would like to separate your Instruments onto different layers, you can freely create new layers and copy/paste your objects between them.

If you choose to go this way, you can rename the layer(s). You should name any newly created layers to match that of the device you intend creating on the layer. To do so, double click on the text area shown alongside as “type in here”, and type in the desired name. Press the  key and you’re done.



2.6 Manual Instrument Setup

This section of the chapter discusses the manual creation of objects, should the Various Multis not contain an Instrument or Environment suitable for your MIDI device(s).

Input and Metronome Objects


Your “Vanilla/Autoload” song will contain these objects on the Click and Ports layer, so there is no need to perform these steps. This section does, however, contain info on the setup of channels/ports and note assignments for the metronome. You can skip to the following section, if you own a MIDI device which is not contained in the “Various Multis” song.

Creating and Cabling the Input Objects

- Select the “Click & Ports” Layer from the Layers menu.
- Select **Physical Input** from the Environment window’s **New** menu.
- Select **Sequencer Input** from the Environment window’s **New** menu.
- Click & hold on the **Sum** outlet (triangle) of the Physical Input object, and drag a cable to the Sequencer Input object.

Creating the Metronome Object

- Select **MIDI Metronome Click** from the Environment window’s **New** menu.





- Assign the appropriate output port, and MIDI channel, plus any transpositions necessary for the **Note** values, changes to velocities etc. In the image alongside, you will see the default settings for a GM (General MIDI) metronome click—i.e. assigned to MIDI channel 10, and using specific note values—C#1 is assigned to a sidestick sound in the standard GM drum kit.
- Save this Song. Give it the name “Vanilla” or similar.

Setting up Single Instruments

This section covers the set up of a single instrument, if applicable to your studio. Maybe you do not have such a simple, mono-timbral sound generator. If not, browse to the Multi Instrument or Mapped Instrument sections.

- Go to the Layer named “MIDI Instr.” by selecting it from the Layers menu.
- For the devices that receive on only *one* MIDI channel but do not have a “drum” mode—remember that “drum” mode instruments have multiple sounds on one midi channel—create an Instrument via the **New > Instrument** menu function. This can include effects processors, electric pianos, mixing devices, such as the Yamaha 03D and some older synthesizers—e.g. the Yamaha DX7 and several analog synthesizers.
- Repeat this step for each device which receives on only one MIDI channel.
- Set the port and channel of each Instrument by using the mouse as a slider on the **Cha** parameter, and **Port** flip menu (as shown), found in its Parameter Box to the left of the Environment window.



- Now give each Instrument a name by selecting the name tool, indicated below, and clicking on the name below the Instrument(s). Simply type in the appropriate name and press . As a word of advice, it's better to use short names, like “DX7”, “Pulse” etc. rather than “Waldorf Pulse Mono Synthesizer”.



- After setting up your Instruments, save your song via the **File** > **Save** menu. This will save your changes to the “Vanilla” song file.

Important!



Setting up Multi Instruments

To set up a Multi Instrument, if applicable to your set-up, refer to your list and follow these steps for *each multi-channel device*:

- Click on the Layer flip menu, and select the “Instruments” layer.
- Create a Multi Instrument by choosing the **New > Multi Instrument** menu option. This will create a Multi Instrument object onscreen.
- Click on the numbered boxes—1 to 16—within the Multi Instrument to activate its “sub-channels”—i.e. MIDI channels. Only select the number of channels that your MIDI device supports.
- Click on the Icon (It looks like a MIDI port) at the *top* of the Multi Instrument object, which will highlight it as shown in the diagram below.



In the image shown above, the Arrange and Environment windows have been set up side-by-side. A Multi Instrument has the first 3 channels activated.

- Set the appropriate physical port for the Multi Instrument by clicking on the **Port** flip menu in the Multi Instrument's parameter box to the left of the Environment window.
- By default the **Cha** value is set to **All**. This is a global channel setting for the entire Multi Instrument object, and should be left alone. Changing the value will override any individual sub-channels activated within the Multi Instrument. If changed, it would “force” all data, regardless of sub-channel, to this global channel setting.
- Repeat the above procedure for each multi-channel MIDI device.

Important!

Important!

In the diagram, note that:

- Channels 4 to 16 have a diagonal line through them, which indicates that these channels are *not* active in this Multi Instrument.
- The entire Multi Instrument has been sent to the “Creative Sou” port. This indicates the Creative SoundBlaster MIDI interface installed on the computer that was used for the image.

- The **Cha** setting is set to **All**. What this means is that the entire Multi Instrument object will send MIDI data on all 16 channels. If this value was set to a specific channel, the sub-channel settings (1—16) of the Multi Instrument object would be overridden and re-routed to a single channel—i.e. the *global* channel for the entire Multi Instrument. As discussed above, the global **Cha** setting for the Multi Instrument should be set to **All**.

Setting up a Multi Instrument is as simple as selecting **New > Multi Instrument**, assigning the appropriate output **Port** if you have multiple ports (On MacOS—USB7 = USB Port 7, M3 = Modem port 3, P4 = Printer port 4 a.s.o.) and activating the required number of MIDI channels—i.e. the *sub-channels*—for your MIDI synth.

It is advisable to only select the number of MIDI channels that your synth actually requires. E.g.—Kawai K5000—4 channels, Waldorf Microwave XT—8 channels, Roland JV2080—16 channels. This reduces the amount of clutter in the Track List’s hierarchical menus, making things easier to find and manage.

Tip

After setting up your Instruments, save your song via the **File > Save menu**. This will save your changes to the “Vanilla” song file.



Important!

Customizing a Multi Instrument

Once you’ve set up a Multi Instrument, there are a number of changes you can make to it which aid in the use of Logic. Following is information on how to make these customizations. While changing the color(s) and icon(s) aren’t absolutely *essential* changes, it won’t hurt. We do, however, strongly recommend that you make changes to the name of the Multi Instrument and also the patch list names within the Multi Instrument. Selecting patches by name is much easier than trying to deal with program change numbers.

Object Color

When recording, the sequence objects in the Arrange window can automatically be assigned a color, which makes viewing and managing tracks much easier.

- Select a sub-channel in your Multi Instrument by clicking on the corresponding number within the Multi Instrument “grid”.
- From the **View** menu, select **Object Colors**, or use the Key Command. This opens a floating color palette which allows you to assign a color to each channel. 
- Simply select each channel, by clicking on it with the mouse, and then the color for each channel—again with a mouse click.
- When you’re done, close the Color Palette via the close window button in its top left corner or the Key Command used for opening the Color Palette. 

Instrument Icon

While you’re selecting your sub-channel colors, why not assign icons for each as well? Again, a convenience which makes it easier to keep track of your Instruments and their channels.

- Select a sub-channel in your Multi Instrument by clicking on the corresponding number within the Multi Instrument “grid”.
- In the parameters box to the left of the Environment, click-hold on the icon itself. This will open a flip menu, from which you can select an icon of your choice.
- Simply select each sub-channel, then the icon for each channel.



You can prevent objects (including sub-channels in Multi Instruments) from appearing in the Arrange window Track List, by unchecking the **Icon** checkbox. This is also useful for hiding/disabling a sub-channel that has been activated by mistake.

Tip

Instrument Name


Select the name tool, highlighted in the toolbox to the left of the image below, then click in the space shown below the Multi Instrument and type in an appropriate name for your MIDI device.




Patch Names

Rather than selecting patches via meaningless—and difficult to remember—program change numbers, you can select patches stored in your synth's memory by name. To customize patch list names for your Multi Instrument:

- Double-click on the icon at the top of the Multi Instrument. (It looks like a MIDI port) This will open a window similar to the image shown below.



- To rename the default GM patch list entries, simply double-click on the names—one by one—and type in the appropriate patch name. Note the “New Name” entry to the top left of the list.
- Following the naming of each entry, press , or simply use your mouse to double-click on another entry.
- When finished, close the Multi Instrument patch list.
- Repeat all steps for the creation (and customization) of *each* Multi Instrument object which corresponds to the physical MIDI synth/modules in your studio.

You can also type out a list in SimpleText or your word processor, and use the copy/paste options, accessible via the downwards arrow to the right of the **Bank Message** flip menu.

Tip

Advanced Patch List Function—Bank Select

Many synthesizers contain more than 127 sounds. If you own a device of this type, this section—and possibly the next—will be of interest, and use, to you.

As an additional function, accessible from the patch list window, you can assign patches to other *banks* of sounds (up to 14) by using the **No. Bank specified** and **Bank Message** flip menus. This will allow you to access patches beyond the standard 127 allowed by MIDI—obviously dependent on your synth's capabilities.

To activate new banks—select any of the 14 possible banks from the **No. Bank Specified** flip menu. Most modern synthesizers use Bank Message: Control 32, so it's unlikely that any changes will need to be made in the **Bank Message** flip menu. We suggest that you take a look at this flip menu, as some specific synthesizers and modules are listed here, which use a different bank select protocol. If you own a synthesizer which is named in the list, select it with the mouse. If you own a synthesizer which has multiple banks, but does not use the standard Control 32 (or Control 0) message for bank select, please refer to the following *Custom Bank Messages* section.

Each of the new banks will have its own patch list which, by default, will use the names of the first bank. To rename the patches, please follow the instructions


Do *not* use the *Bank* functions if you only have one bank of patches in your synth. Initializing new banks requires the use of more memory for the object, thereby making the object, and subsequently your song files, larger.

Tip

Custom Bank Messages

Should you own a synth with an unusual scheme for bank selection, you will need to set up “Custom Bank Messages”. Here’s how to do it without trying to understand the hexadecimal listings found in the back of your synth’s manual.

- Select **New > Monitor**.
- Run a cable *out* of the Physical Input’s Sum port *in* to the Monitor object.
- Cable from the Monitor object *in* to the Sequencer Input object.
- Select the various banks from the *front panel* of your synth, using it’s buttons/menus.
- Write down the various numbers that appear in the Monitor objects’ window, each time you press the button(s) on your synth.
- Once you’ve done this for each bank in the synth, select the Multi Instrument object, and choose the **Options > Define Custom Bank Messages** function. A window which looks like the diagram below will launch.



Position	Status	Cha	Num	Val	Length/Info
----- Start of List -----					
Bank 0 (a)	Control		0	57	Bank MSB
Bank 1 (a)	Control		0	1	Bank MSB
Bank 2 (a)	Control		0	2	Bank MSB
Bank 3 (a)	Control		0	3	Bank MSB
Bank 4 (a)	Control		0	4	Bank MSB
Bank 5 (a)	Control		0	5	Bank MSB
Bank 6 (a)	Control		0	6	Bank MSB
Bank 7 (a)	Control		0	7	Bank MSB
Bank 8 (a)	Control		0	8	Bank MSB
Bank 9 (a)	Control		0	9	Bank MSB

- Double click in the **Val** column, and type in the numbers that you’ve written down for *each* bank and you’re done.
- You will need to type the appropriate patch names into the patch list (as discussed in the *Patch Names* section, from page 83 onwards), should you wish to select patches by name in these higher banks.

Once set up, whenever you choose a program or bank from the *Track Parameters* box in the Arrange window, it will automatically send the appropriate bank/patch number to your connected MIDI device.

As always, after making any customizations to your Multi Instruments, ensure that you save your song.


Important!

Setting up Mapped Instruments


As with the other instrument types, the creation of a Mapped Instrument, is achieved by selecting **New > Mapped Instrument**. Assign a port and channel as per the Instrument object, covered in the *Setting up Single Instruments* section, from page 78 onwards.

Ensure that the **Cha** setting for the Mapped Instrument (Drums Mapped, in the diagram) matches the “drum” channel in your synthesizer/module.

Setup for Multi Timbral Synths with a Drum Channel



If your drum module or synthesizer has more than one drum kit, cable it as shown. The reason for cabling a multi timbral synth in this fashion is to take advantage of the Multi Instrument object’s ability to name patches, as discussed in the *Patch Names* section, from page 83 onwards. Note that when you cable the Mapped Instrument object into the Multi Instrument object, you will be prompted with the following warning dialog box. Click on the **Remove** button.



Set up patch/bank names for your different drum kits within the Multi Instrument, as per the instructions in the *Patch Names* section, from page 83 onwards. Double-clicking on the mapped instrument object will open a window like the one shown below.

TAMB.	F#2	0	Base 1	•	---
RIDE BELL	F2	0	Base 1	×	Cymbals
CHINA	E2	0	Base 1	×	Cymbals
RIDE 1	D#2	0	Base 1	×	Cymbals
High TOM 1	D2	0	Base 1	•	Toms
CRASH 1	C#2	0	Base 1	⊗	Cymbals
High TOM 2	C2	0	Base 1	• ↓1	Toms
Mid TOM 1	B1	0	Base 1	• ↓2	Toms
Open HH	A#1	0	Base 1	⊗	HiHat
Mid TOM 2	A1	0	Base 1	• ↓3	Toms
PED HH	G#1	0	Base 1	×	HiHat
Low TOM 1	G1	0	Base 1	• ↓4	Toms
Closed HH	F#1	0	Base 1	×	HiHat

In this window you can:

- Assign individual notes to be within a “group” (Kick, snare, hats, toms etc.)
- Assign a “relative” position—this means you can move the note up or down in semitone steps *graphically*, which does not affect the pitch. It does, however, affect the way the note *appears* in the Score editor.
- Change the appearance of the note head.

All of these functions are useful for scoring. As an example of where this would prove invaluable, would be in the case of the GM drum map. For any module which strictly adheres to this standard, there will be a 5 octave tom (tom) kit. If you used a tom on note C2 and another tom from C5, your score would look awful, to say the least.

Additionally, in the drum map window you can change the Base MIDI channel, set via the Mapped Instrument’s **Cha** parameter (normally 10 in GM devices), and **Cable** channel. This allows you to assign particular note values (and therefore, drum sounds/samples) to individual MIDI channels.

Further facilities allow the reassignment of an input note to a different output note, and the setting of velocities on a per-note basis. This type of functionality is useful for sampling (and other) keyboards which don't have a GM drum note assignment.

After setting up all of your Instruments, save your song via the **File > Save** menu. This will save your changes to the “Vanilla” song file.

Important!

2.7 Creating Audio Objects

That's about it for the MIDI input and output objects *required* for getting MIDI data into, and out of, Logic. If you have no desire to extend your Environment beyond this basic MIDI functionality, you can leave things as they are. If you wish to go further: There are a number of additional objects which can be used for remote control of the MIDI device's parameters, discussed in the *Environment Controls* section, from page 95 onwards. You may also make use of the vast number of Environments found on the Logic program CD and the Internet.

By default, a number of audio objects were created when your first installed the program.

We recommend that you do not create further audio objects of any type until they are actually required for a project. The creation of additional audio objects increases the need for system resources, placing undue strain on your computer. In other words, creating 64 audio playback tracks “because you can” is pointless and wasteful if you only require 8 audio playback tracks.

Important!

As mentioned, Logic features several “types” of audio objects. These different *types* are based around the same fundamental Environment object—namely the Audio object—but each has distinct facilities. The “cabling” between audio objects—which deals with the audio signal flow—is automatically (and invisibly) connected by Logic, as new audio objects are created

and assigned. This invisible cabling follows a fairly standard signal path, normally found on a mixing console, with audio channels, busses, master faders etc. As such, the Logic mixer will immediately be familiar to you if you've had any experience with mixing consoles.

All audio objects, with the exception of the Master Volume fader, accept the use of software “plug-ins”. Plug-ins are DSP (Digital Signal Processing) algorithms which are processed by the computer's CPU. These algorithms can include audio effects such as: reverb, chorus, flanging, compression, equalization and many more processes. A special Audio object “type”—the Audio Instrument—allows the use of software plug-ins which emulate synthesizers, samplers and drum machines.

Audio Object

The Audio object is, as mentioned, the fundamental object used for audio functionality in Logic's Environment. By default, any Audio object created will be assigned to the first available *playback* channel, or “Audio Track”.

Audio Input Object

As the name suggests, the Audio Input object allows the processing of audio streams entering Logic. This means that incoming audio can be monitored (i.e. heard) with effects. A separate Audio Input object can be created and assigned for each physical input (or input pair) of your audio interface hardware. Note that Audio Input objects do *not* need to be created, in order to get audio in to Logic. These objects simply allow the *processing* of audio on input.

Audio Bus Object

This is just like a bus/group on an audio mixing console. It acts as a send/return for Audio Track (playback), Audio Input and Audio Instrument objects, when effects are inserted. It also acts as a “group” fader, where multiple audio channels can be routed to it, and volume or pan can be adjusted globally for all “grouped” channels. Busses can be routed to Output objects (Master Faders) or to other busses.

Audio Output Object

This is Logic’s Master Output object, equivalent to the master output fader(s) on a mixing desk. If you have audio hardware which features multiple outputs, you can set up an Audio Output object for each physical output—or output pair (Out 1 and 2, Out 3 and 4 etc.). It also acts as a “group” fader, where multiple audio channels can be routed to it, and volume or pan can be adjusted globally for all “grouped” channels. This fader type features a **Bn**ce button which is used to bounce (digitally combine, or mix) any incoming audio—from the other fader types—to a mono, stereo or multiple Surround-format audio files.

Audio Instrument Object

This is a unique audio object in Logic. It supports the use of software-based “instrument” plug-ins. These “plug-ins” include Emagic’s **ES 1** and **ES2** Synthesizers, **EHS 24** Sampler and **EUP 88** Piano plus third-party VST2.0 instruments. Although the Audio Instrument object looks similar to Logic’s other audio objects, it supports MIDI *note* input, which the others do not. This enables appropriate plug-ins placed in the *top* insert “slot” of Audio Instrument channels to be “played”, just like an external MIDI synth, sampler or module.

Master Volume

This, as the name suggests, is a Master Volume control for the entire mixer. It is Logic’s equivalent to the Control Room fader on a mixing desk.




The diagram shows—from left to right—the Audio Track, Audio Input, Audio Instrument, Bus and Output faders. Please note the “Cha” entry in the parameters box for the selected “Audio 1” Track fader. Another point to note are the surround pan controls on three of the first four faders. Each can be set to a different Surround format. Logic can use any of 12 Surround formats simultaneously, on a per-channel or per-bus basis. Additionally, note the Touch, Read, Latch, Write and MIDI text windows on each fader.

Each audio object, regardless of *type*, is created in the following way.

- Open the Environment via the **Windows** menu or Key Command
- Select the “Audio” Layer from the Layers menu.
- Create an Audio Object by selecting **New > Audio Object**. This will generate a small “waveform” icon onscreen.
- Double-click on the icon to change its appearance to an audio fader, as shown in the image above.



- Clicking on the **Cha** entry in the Audio object's parameters box will allow you to select the audio object *type* via a hierarchical menu, as shown in the following diagram.



- It is very important that no two audio objects are assigned to the same *Track*, *Instrument* etc.—i.e. do not create two audio objects that are assigned to Track 1, or Instrument 3, for example
- The **MIDI channel** entry determines the channel used by the Audio Object. By default, this will match the Audio Object's Track number—i.e. Track 1 will be set to MIDI channel 1, Track two to channel 2 a.s.o. Again, ensure that no two objects of the same *type* are assigned to the same MIDI channel. There is no need to concern yourself too much with this parameter. It is of little consequence to Logic's new Track Automation system, and is primarily of use for compatibility with songs created in older Logic versions.

Important!

You should only set up as many Audio objects as you think you will reasonably need. In other words, don't set up 64 audio playback channels if you are only likely to use 16 tracks of audio playback in your normal "day to day" use of Logic. The reasons for this:


Tip

- Each channel (audio object) occupies an amount of onscreen space, and when dealing with an Environment that has, say 40 audio playback objects, you will find yourself scrolling endlessly through faders when using the Environment's audio mixer (**Audio > Audio Mixer**).
- Each audio object uses system resources, even when not in use.

Similarly, you should only set up as many Bus, Audio Instrument and Audio Input objects as you think you will need (and your hardware, and Logic version allows).

Although hardware and version dependent, Logic Platinum will generally create the following number of audio objects when first installed:

- 24 Audio Playback Channels (Audio Tracks)
- 24 Audio Instrument objects
- 8 Bus Objects (Returns)
- As many Master Output objects as your hardware supports. These are generally displayed as *stereo* objects for each stereo output pair—i.e. an object for 1 and 2, another for 3 and 4 a. s. o.
- A Master Volume fader


 Logic Audio (formerly Silver) will create fewer Audio Instruments, for example, so don't be too concerned if your Environment Audio layer doesn't feature all of the objects, as listed.

If you find that you need, or would prefer, more (or fewer) of a particular type of audio object as you work with Logic, you can return to the Environment and simply create (or delete) them, as per the steps outlined. Note that the maximum number of each audio object type which can be created, is primarily determined by the version of Logic you are using. As an example, Logic Platinum allows up to 16 busses, Logic Gold up to 8, and Logic Audio 4.

2.8 Setting up Tracks

At this stage, you should have a functional Environment that allows MIDI and Audio input and output. Congratulations!


There is one final step, which we strongly recommend, to complete the customization of your default song.

Save your song, if you haven't already done so, as “Autoload” *in the Logic program folder*. This is done via the **File > Save As...** menu. In the ensuing dialog, browse to the appropriate folder, if necessary, and type “Autoload”, then press .

Important!




Open the Arrange window via the **Windows** menu or Key Command. You will note that the Track List is filled with “No Output” entries.



As you can see in the image, the hierarchical flip menu can be used to replace the “No Output” entries with any Audio or MIDI object created in the Environment.

Create a number of Audio tracks, MIDI instrument tracks and Audio Instrument tracks to suit you. It is unnecessary to create a track for every channel of your MIDI synths, or for every audio channel—but one or two channels for each synth, a couple of audio instruments and four audio tracks should be

Tip

fine to start with. Delete any unused tracks by clicking on any “No Output” track and pressing the  key. As you do this, the next track in the list—working from top to bottom—will automatically be selected.



Once done, save your “Autoload” song via **File > Save**. Whenever you launch Logic, or create a new song, this Autoload file will automatically be opened—with audio tracks, MIDI tracks and Audio Instrument tracks prepared—and ready for immediate use.

Important!



There are many further customizations that can be made to the Autoload song, both in the Environment and elsewhere in the program, as preferences. We’ll introduce you to these as we continue working through the Introduction Manual. You can always make changes—which can be saved in your Autoload—as you become more familiar with how you prefer using Logic.

2.9 Environment Controls

After setting up all of your Instruments and Audio Objects, you may wish to add some additional objects for control over your MIDI devices.

Note that the addition of these objects is *optional*. They act as *remote controls* for your MIDI devices, and can be used to control virtually any function that your MIDI devices are capable of understanding. If you do not wish to incorporate this type of functionality into your Autoload, you can skip this section, and return to it at a later stage, should you change your mind.

Tip

The **Windows > Track Mixer** automatically creates a fader for each channel, including sub-channels, of each Instrument object in the Environment. Each MIDI fader in the Track Mixer also allows the use of up to four different types of

controller, which you can freely reassign. If your MIDI mixing needs do not extend beyond manipulation of volume, pan, and filter cutoff and resonance, for example, then there is no need to create further Environment objects.

If you have a grander vision, this section of the Introduction Manual will provide you with examples for the set up of faders and knobs for control of volume and panning. For single Instruments, a single fader and pan pot will suffice. For Multi Instruments, faders will need to be created and assigned appropriately for each MIDI channel *used* by each Multi Instrument. We'll show you some great shortcuts which will speed up the process.

For control over other synthesizer functions, such as filter cutoff and resonance, or envelope controls, the procedures you will learn here can be applied. Note that this is entirely dependent on the capabilities of your synthesizer, and the controllers used will vary from machine to machine—if they can be used at all. As such, you will need to consult the documentation of your synthesizer(s) for information on controller numbers.

If you own a GM, GS or XG synthesizer, you create a GM Mixer object which offers control over volume, pan and several other continuous controllers, plus effects functions. See the *Setting up a GM Mixer Object* section, from page 104 onwards.

Setting up a Single Fader

To set up a fader, simply select **New > Fader**. There are, as you will see, a number of choices available in the **Fader** sub-menu. For now, choose **Auto**. This will generate an onscreen fader. Faders can be assigned to any MIDI channel, and require no special cabling to be functional. Fader objects can *generate* MIDI data of different types that can be:

- Sent out of Logic.
- Recorded.

Fader objects can also respond to incoming MIDI messages and can convert these messages to different types of MIDI data.



The fader in the image has been named “Vol 1”. Also take note of the parameters box to the left. In particular, pay attention to the **Out** and **In** assignments, plus the **Channel** and **-1-** entries. As you can see, these are matched.

Click on the **Out**, **In** and **-1-** entries to check out the options available in these menus. The value of **7** assigned to the **-1-** entries corresponds to the MIDI Controller number for “Volume”. MIDI Controllers are often called *continuous controllers*, and are regularly displayed as follows in MIDI device manuals: “CC#7” or “CC7”—Volume.

Controller Input

If you were to change the value of the **-1-** entry, under the **In** section to say, CC#19 (a value of **19 = General # 4**, in the flip menu), the fader would only respond to controller 19 messages coming *in* to it on MIDI channel 1. All other messages would be ignored. This ability (of the fader object) to ignore, rechannelize and convert MIDI data on the fly is particularly useful for external hardware controllers.

As an example, your MIDI keyboard may have a single slider or a modulation wheel as it’s only hardware control option. Using the remapping facilities of the Fader object, you can use a single hardware controller for manual manipulation of volume

or other types of MIDI continuous controller. Obviously, having multiple faders on an external controller makes life easier, but in many cases, even multi-fader external controllers will only transmit on a single MIDI channel or will use the same CC number on different MIDI channels. Using the fader object's *Controller Input* facilities allows you to specify the incoming MIDI channel, CC number data that the fader will respond to.

Please refer to your synthesizer or MIDI device manuals for specifics on controller numbers and their operation.

Controller Output

The **-1-** entry under the **Out** section, allows you to assign the type of continuous controller *sent* by the fader object. As shown in the example above, CC#7—Volume, is being sent by the fader. To change this fader's functionality to act as a Pan control for MIDI channel 1:

- Click-hold on the number **7** alongside the **-1-** entry, under the **Out** section.
- Select **CC#10—Pan** from the flip menu.

Most people normally associate pan controls with a knob. To change the appearance of the Fader to a Rotary knob.

- Click on the **Auto Style** text in the fader's parameters box.
- Select any of the *as Knob* styles available. Selection of Knob style 2 is shown alongside.
- You can also change the appearance of an “Auto Style” fader by click-holding on the small box to the fader's lower right and dragging the fader's outline to a different size or shape—i.e. square as opposed to rectangular. When you release the mouse button, the fader's appearance will change.


You can directly interact with the fader object—and therefore generate data—by click-holding on it, and moving the mouse. The movement of the mouse will vary, dependent on the style of the fader. e.g. horizontal movement will not affect a vertical fader.

Auto Style
vertical 1
vertical 2
horizontal.1
horizontal.2
as Knob 1
as Knob 2
numerical
as Button
as Text
vertical 3
horizontal.3
as Knob 3
numerical3
as Button3
vertical 4
horizontal.4
as Knob 4
as Vector
vert.Mute
vertical 5
as Knob 5
Button 5
vertical 6
as Knob 6
Button 6

Setup Shortcuts for Multiple Faders

Let's look at some shortcuts for building an automated mixer.

- Select a layer on which you have created a Multi Instrument
- Create a new fader, if one doesn't exist.
- Hold the **ctrl** key down, and while doing this, click and drag the fader object to the right. Release the mouse button and **ctrl** key. This should have created a copy of the fader object.
- Rubber-band select the two fader objects by clicking outside either fader, and dragging, while the mouse button is held down. Drag the outline box until both faders are highlighted. Below, four fader objects are selected.



- Once highlighted, release the mouse button.
- Hold the **ctrl** key down, and while doing this, click on either fader object and drag to the right. Release the mouse button and **ctrl** key.
- You should now have 4 faders onscreen. Repeat until enough faders have been created for all *used* MIDI channels of your connected MIDI instrument.
- Rubber-band select *all* faders, double-click on the **Multiple sel** text in the parameters box, and type in **Vol 1**, as shown.
- Note that all of your faders have been automatically, and sequentially, renamed **Vol 1** to **Vol 16**.
- Last step is to change the **Control Out** and **Control In** MIDI channel for *each* fader. By default, all faders will be assigned to MIDI channel 1 for both **Control In** and **Out**. You will need to change the “Vol 2” fader object to MIDI channel 2, the “Vol 3” fader object to MIDI channel 3, the “Vol 4” fader object to MIDI channel 4 a.s.o.
- This is done most efficiently by selecting the **Options > Apply Buffer Template to > Definition, Channel Increment** function.



This same set of procedures can be applied to fader objects assigned to *any* other controller. As an example, if you wanted to set up pan pots for your mixer, you could simply rubber-band select your existing faders, and copy them using the technique above.

While all copied faders are selected;

- Rename them to “Pan 1”.
- Change the **Output** controller number from **CC#7** (Volume) to **CC#10** (Pan).
- Change the faders to knobs.

You can also copy existing faders between Environment *layers* by selecting the standard **Edit > Copy** and **Edit > Paste** functions.

Tip


How to Automate Faders

While not necessary for the recording and playback of volume, pan and other types of MIDI controller data, it can be helpful to see your faders moving during playback. The advantage is that when you move to different sections of your arrangements and songs—when in *pause* or *play* mode—your faders will update to reflect the current volume, pan (or other continuous controller) setting for each channel on each MIDI device. This at-a-glance overview can be very helpful when trying to isolate a part that isn’t “sitting” properly in your mix.

Note that the **Windows > Track Mixer** is fully automated, and that Logic 5’s Track Automation system provides graphical automation track(s) in the Arrange window. The automation track(s) allow a far more accurate overview of various parameter settings/levels than is possible with any onscreen fader.

The “Mix” Object

The best solution for this type of “flying fader” automation (outside of using the Track Mixer) is to set up a *mix* object for all channels to be recorded to. See the diagram below.




In this example, the output of the “JV Mix” object has been routed in to the Pan and Vol objects. If you wish to set up a similar set of faders and a Mix object in your own Environment, follow the steps outlined in the preceding sections and this section, substituting JV Mix for your own object name.

The JV Mix object is simply an *Instrument* object, created via the **New > Instrument** menu. It’s icon has been changed to that of a Mixer and the **Cha** parameter has been set to **All**.

- Create your own “Mix” object using this method.
- To set the **Cha** parameter to **All**, click-hold on the Instrument (Mix object) parameter box **Cha** value of **1**, and drag the mouse *down*.
- As a nice shortcut for changing the icon, you can double-click on the existing Instrument icon, in the parameters box, and type in **304**. This will change it to the mixer icon shown.
- Use any of the naming techniques you learned earlier to rename the object. It is recommended that you give it a name which is relevant to the device it is controlling.
- Note that all of the Pan and Vol fader objects have been cabled *serially*—i.e. one after the other. To cable your faders in this fashion, rubber-band select them and select the **Options > Cable Serially** menu item.
- When cabling the Instrument—i.e. JV Mix—object into the first of your faders, as per the image, you will see the following dialog box. Select **Remove**.

Tip





- After doing so, note that the port previously shown in the parameters box will now display **No Driver** or will appear as a blank space above the **Cha** line.
- Repeat this procedure for each channel, of each device (where applicable), on each layer.
- Once done, save your “Autoload” song via **File > Save**.

Important!

Using the Mix Object

Please give the following a try, to ensure that your cabling is correct, and to get a feel for using the Mix object/Track.

- Select the JV Mix object in the Arrange window’s Track List by click-holding on any Track name and scrolling through the hierarchical flip menu. Once the JV Mix object is found, release the mouse button.
- Reposition your windows to allow the viewing of the Environment layer on which the JV Mix object and your faders exist, plus the JV Mix track in the Arrange window.
- Activate **Record** via the Transport Bar or Key Command.
- Move your faders and knobs. As you do so, you’ll note that data is recorded onto the JV Mix track.
- Once done, stop recording by pressing the **Stop** button on the Transport Bar, or via the Key Command.
- On playback, the output of the JV Mix track/object is routed *in* to the various faders and pan pots causing them to move in response to the incoming data.



Recording Preferences

Logic’s Recording preferences have a part to play in the way your sequence data—controllers or MIDI notes—appears. These preferences will affect the way that any MIDI Mix automation appears in the Arrange window.


 Note that this does *not* affect the Track Automation system.

Open the **Options > Settings > Recording Options...** menu. You will see several options here, which allow you to “merge” or “auto create” tracks. We will discuss these recording options in more detail later, but for now, keep the following in mind:

The **merge** options will combine all recorded fader movements into a single sequence on the JV Mix track. Recording all of your MIDI mix information to one track keeps things neat onscreen, and all mix automation data in the one place. Editing is easier because you don’t need to open several Event List or HyperEdit windows to deal with multiple tracks. Additionally, if you want to isolate data, you can simply use the **Select Equal** or **Similar** filters in your editing windows, which we’ll discuss in the next chapter.


If the **auto create** options are selected, your automation data will be recorded onto several discrete sequence objects, as you record individual fader movements on each “pass” or “take”. The advantage of this is that your fader automation tracks will be recorded on a per-fader basis, with a discrete sequence appearing in the Arrange window for each fader’s data. While this offers some advantages, you can quickly end up with a number of sequences stacked on one track—i.e. the JV Mix track, or you can end up with a number of tracks. Either way, your Arrangement can quickly become filled with automation sequences and these sequences will be difficult to manage and edit.

Try both the merge and auto create options as you become more familiar with working in Logic, and set the appropriate preferences.

 We strongly recommend the use of the Track Automation system, which we’ll discuss a little later in the Introduction Manual.

Setting up a GM Mixer Object

This object is unique in that it is a hybrid object. It combines some features that seem more like those of a Multi Instrument object, plus a number of faders, pan pots and more into a single unified surface. It is ideal for *remote control* of General MIDI, GS or XG synthesizers. If you own one of these types of devices, creating a GM Mixer Object is the quickest way to set up all of the faders, pan pots and more in the Environment.



- Select the layer which contains your GM synth from the Layers menu.
- Create a GM Mixer object by choosing **New > GM Mixer** in the Environment window.
- Set the appropriate port for the new GM Mixer object by clicking on the **Port** flip menu, found in its Parameter Box to the left of the Environment window.
- Repeat these steps for each GM, GS or XG device.
- Once done, save your “Autoload” song via **File > Save**.

Important!

2.10 Environment Processing

As briefly discussed at the start of the chapter, you can cable various objects together to create different types of “machines” or processors for your MIDI data.

This section will touch on a few of the other data processing objects you will find in the Environment, and will offer some practical examples of where they may be useful to you—both musically, and on a technical level.

As the old adage goes, a picture’s worth a thousand words. We’ve taken this a step further and for these examples, you’ll find an accompanying song file.

The point behind this section of the chapter is to introduce you to some creative ways of using the Environment objects and a couple of key concepts. Namely:

- Objects can often be used for tasks that extend beyond their obvious use.
- Objects, when combined, can perform tasks that utilize a little of each object’s functionality to create a new processor. This new multi-object processor may perform a function that is unrelated to the functionality—obvious or otherwise—of the objects.

Important!

We encourage you to spend some time—over the coming months—experimenting with each object in the Environment, to familiarize yourself with their practical and possible uses.

The Chord Memorizer

- Please load the *Chordmemorizer* song file, via **File > Open**. Browse to the install directory for this song. It is set up for use with a GM device.
- Once opened, press the **Play** button on the Transport Bar, or use the Key Command.




The screen is split into three windows, showing the Arrange, the Matrix and Environment, from top to bottom. As you can see, the Arrange window contains a sequence on the “Chord Memorizer” track. The Matrix window, in the center, shows the contents of this sequence. The Environment window at the bottom displays the Chord Memorizer object, which is cabled into both the Cha 1 and keyboard objects.

As the sequence plays, and cycles, you’ll see that the Matrix editor only displays single notes, yet you can hear chords and see chords being displayed in the keyboard object in the Environment. The Chord Memorizer object will trigger a user-defined chord when it receives a single MIDI note event.

Stop the sequencer by pressing **Stop**.



Double-click on the Chord Memorizer object in the Environment.




Click on the notes from C2 through to G2 on the *top* keyboard. As you do so, you’ll note that the chord changes in the bottom keyboard. To change voicings in your chords, simply click on individual notes in the lower keyboard. To deactivate a note in the chord, simply click on the highlighted note a second time.

The obvious use of the Chord Memorizer for single note triggering of chords could be extremely useful for a non keyboard player, allowing fast chord runs to be recorded.


Alternate Scales

Another use for the Chord Memorizer could be for alternate scales. Individual notes can be reassigned to other notes. To view this in action:

- Press the **3** key on your computer's keyboard to recall Screenset 3. In the Track List of the Arrange window, you'll see the following on tracks 12 and 13.



- Click on the blue **M** button on the Tuner track once, so that it turns gray.
- Click on the gray **M** button on the (Chord Memorizer) track once, so that it turns blue as shown below.



- Click on the Tuner track in the Track List so that it turns a light gray. This will select the track and will update the linked Score and Matrix windows to display the contents of the MIDI sequence on the Tuner track.
- Press **Play** on the Transport Bar, or use the Key Command.



As you can see in both the Matrix and Score displays, a Pentatonic scale—the white notes from C upwards—is being played. What you can hear, however, is being routed via the “Tuner” object, which is a second Chord Memorizer that has been set up to change incoming notes to other notes.

- Press **Stop** via the Transport Bar, or Key Command.




Auto Accompaniment

Any sequence can be routed via the Chord Memorizer to play an accompaniment part, based on the original sequence. In conjunction with other objects, you can limit the accompaniment to individual notes, or selected notes within the chord, rather than simply doubling up the entire part with a layered sound.

- Click on the gray **M** button on the Tuner track once, so that it turns blue.

- Click on the blue **M** button on the (Chord Memorizer) track once, so that it turns gray as shown below.




- Click on the (Chord Memorizer) track in the Track List so that it turns a light gray. This will select the track and will update the linked Score and Matrix windows to display the contents of the MIDI sequence on the track.
- Press **Play** on the Transport Bar, or use the Key Command.
- Click once on the Cable Switcher object as the sequence is playing. You will hear a string part playing specific notes within the chord. The cable Switcher object is simply used to switch between cable connections to other objects. In this case, it is used to switch the only cable connection on or off—i.e. connected or disconnected to the Transformer object, which in turn is routed to Cha 2—an Instrument object.



The Transformer Object

Please double click on the Transformer object. It will open a window which looks like the following.



Without going into extensive detail here, the Transformer object is used to “transform” one kind of data into another. In the Environment window, the Transform object does this in realtime. To explain the settings used in this example:


- The top flip menu is set to **Apply Operation & Filter non-matching Events**. This means that it will perform any transform operations specified in the **Operations** box and will ignore any event which does not match the criteria set in the various **Conditions**.
- The **Status** is **equal to (=)** **Note** events. All other events—i.e. any MIDI event that is *not* a note event, will be ignored.
- The **Cha** is set to **All**, which means that MIDI note events on any MIDI channel will be allowed Thru, without being processed by any operation.
- The **Pitch** values, as shown, are limited to MIDI note events which fall between (**Inside**) **E3** and **E4**. All note events which are outside this range will be ignored.
- Directly below the **Pitch** condition, an **Add** operation has been applied, with a value of **12**.
- Although it looks a little technical, this is quite easy to understand. All MIDI note events which fall between E3 and E4 will have their pitch values added to by 12. In other words, notes within this range will be transposed up by one octave.
- As the sequence is playing, adjust the range of notes by click-holding and dragging on the upper and lower values—**E3** and **E4**. Adjust the **Pitch** operation value of **12** using the same method.
- Click hold on each of the flip menus and try different options out, to familiarize yourself with the Transformer object.

The Transformer is the most flexible object in Logic's Environment. It can be used for a wide variety of tasks, including use as a simple junction box or a MIDI data filter. Please read the Reference manual for a detailed look at the Transformer.

Tip

The MIDI Monitor Object

Please stop playback, if you have not already done so, and press the 2 key on your computer's keyboard. This will recall Screenset 2 which will be similar in appearance to the following:



This shows several objects set up before the Sequencer Input object, which is named “to Recording and Thru” in the diagram.

The Cable Switcher and Transformer objects can re-route and process data before entering the sequencer, much like the Arpeggiator example discussed at the beginning of the chapter. Please double click on the Transformer objects to see how they are set up. The Pre and Post Process View boxes that you can see are MIDI Monitor objects. The one on the left shows the raw MIDI data, and the MIDI Monitor on the right shows the data after it has been processed by either of the Transformer objects. The keyboard object simply displays incoming note data.

A simple connection from the Physical Input object to the Sequencer Input object will suffice for getting MIDI data into Logic. The more complex routing shown is not necessary, but use of a MIDI Monitor object can prove useful on input, for troubleshooting purposes.

This concludes this brief look at some of the Environment's many objects. Once again, we encourage you to do a little experimentation on your own, and to read the Reference manual for detailed information on each of the Environment objects.

2.11 MIDI Meets Audio

Logic's Environment is, as you've discovered, responsible for getting MIDI and audio data in and out of the program.

We very briefly discussed the Audio Instrument objects in the *Audio Instrument Object* section, from page 90 onwards. As mentioned, the Audio Instrument object is unique among the Audio objects in that it can accept MIDI *note* input.

In practice, playing or recording an Audio Instrument is just like playing or recording a connected MIDI synthesizer or sampler. The Environment's MIDI processing options—arpeggiators, transformers etc.—available to connected MIDI devices, are also available to these Software Instruments.

All you need do is remember the lessons learned in this chapter regarding signal flow. Cable the MIDI processors *in* to the appropriate Audio Instrument object, set up the desired parameters, and get creative.

Please refer to the Environment chapter of the Reference Manual over the coming weeks. It contains detailed information about the parameters of each Environment object. This information will assist you in further enhancing your knowledge and working experience with Logic.

Chapter 3

Using Logic

This chapter covers the basics of many of Logic’s functions by using “hands-on” examples. You will learn how to arrange a song, record a MIDI sequence, record and insert audio regions, plus a number of other techniques. You will also be introduced to a number of preferences which affect the way Logic operates—globally or within specific parts of the program. These preferences can be applied to your Autoload song, if desired. After working through this chapter, feel free to return to your Autoload and adjust the preferences to your liking. Use of Logic’s extensive audio mixing facilities are covered in the following chapter.

Please ensure that Logic is open and that you read through things in order. This is the time to experiment, as this will familiarize you with the functions, general working methods and interactions between the different parts of the program.

Please use the appropriate Key Command—marked as shown—whenever possible. Try to develop this “good habit” from the start by using Key Commands throughout the Tutorial chapter.



As you’re working through each section, take as much time as you need. Repeat any exercises, if necessary, until you feel comfortable with the techniques discussed. This is *your* studio, so there’s no need to watch the clock. Oh ... and don’t forget to have fun!

In order to follow the tutorial you should have:

- installed Logic

- a General MIDI tone generator or an equivalent multi-timbral device (like a soundcard installed in your computer), which is correctly connected to your computer's MIDI interface.

3.1 Adapting the Tutorial Song

As you work through this chapter, use the provided Tutorial song. This song is configured for General MIDI (GM) tone generators, but you won't have any problems using the song with tone generators that don't follow the GM specification. The only difference when using a non-GM device, is that you will manually need to set the sounds and MIDI channels the first time you run the song. You may also need to transpose some tracks. If any of these steps are necessary, be sure to save your changes, so that you don't need to repeat the procedure every time you reload the song—which we will ask you to do several times during this chapter.

Load the Tutorial Song

You can start the Tutorial Song by starting Logic, selecting **File > Open**, and browsing to the Tutorial Song or by double-clicking the “Tutorial” song icon in the Logic folder.



Arrange window with the Tutorial song loaded.

General MIDI Tone Generator

The program change, volume, and pan settings for this song are customized for GM tone generators, and are sent to your device via MIDI. The transmission of these settings happens automatically, if you play the song from the beginning. You will find the settings in a separate sequence—“GM Setup”—at the start of the song. As delays can occur with some synthesizers when they receive program change data, you should mute this sequence after it has been played through *once*.

To mute the program changes:

- Select the mute tool from the toolbox, and use it to click on the sequence named “GM Set-Up”.

The sequence will turn black, to indicate that it is selected, and an asterisk will appear in front of the sequence name. This asterisk indicates that the sequence is muted.



You may also wish to activate the **Muted Objects are textured** parameter in the **Options > Settings > Display Preferences**, to further highlight muted objects.

Tip

Non GM, Multi-Timbral Tone Generators

If you do not have a GM tone generator, you need to consider the following points:

One prerequisite for GM compatibility is that the sounds listed in the following table are available. If necessary, find similar sounds in your own device.

In addition, the drum kit’s note assignment needs to match that of the GM drum map (previously Roland drum map), otherwise the percussion passages in the tutorial will be reproduced with the wrong drum sounds. Set the appropriate receive channels in your multi-timbral synthesizer, and assign sounds similar to those listed in the tables. If you need to rearrange your Drum kit’s note assignments, follow the percussion instrument table in the *Drum Kit* section.

Sounds and MIDI Channels

MIDI Ch.	Function	Sound	Possible Name	Vol	Pan
1	chord	combination piano/E piano	Electric Grand, LA Grand	110	0
2	bass	normal E bass	Pick Bass, Rock Bass, E Bass	127	0
3	accents	muted E guitar	Mute Guitar, Slap Guitar	127	R
4	melody	long dying away melodic sound	Synthbell	100	0
5	carpet	string section	Slow Strings, Pad	90	0
6	accents	wind section	Brass Section	80	L
7	solo	flute-like solo sound	Stream, div. "Solo"	120	0
10	drums	GM-compatible drum set	GM Kit	110	0


Drum Kit

Here is a list of percussion instruments used by the Tutorial song, and their locations. (C3 = Note number #60)

Note	Instrument
C1	Kick
D1	Snare (normal)
E1	Snare (hi)
F1	Tom lo
F#1	HHT closed
G1	Tom mid
G#1	HHT closed short
A1	Tom hi
A#1	HHT open
C#2	Crash
D#2	Ride
E2	Ride Bell

Transposition and relative volume values are only automatically correct with GM devices, so you should play the song a couple of times to see how it sounds after assigning compatible sounds.




Tip

Open the Track Mixer via the **Windows > Track Mixer** menu or  Key Command and use the faders to adjust the MIDI volume levels, if necessary. For further information on the Track Mixer, see the *Track Mixer with Audio Channels* section, from page 156 onwards.



Once you are happy with the sound selection, transposition and level settings, save the song file via **File > Save**.

Starting the Song


- To listen to the Tutorial Song, simply press  on the numeric keyboard.
- To stop the song, press .
- To return to the beginning of the song, push , on the numeric keypad, twice in succession.



These “Key Commands” for the Transport Bar are much faster to use than clicking on the buttons with the mouse.

Throughout the tutorial, we will indicate the appropriate Key Command for various functions. Please use them as you work through this section. It will help you to memorize them, and by the end of the tutorial, you probably won’t even think about “which key?”... you’ll innately know them.


Inside the cover of the Introduction Manual, you will find a Key Command reference chart for the default shortcut keys assigned in Logic.

Give the song a listen now, and press stop—using —once you’re done.



3.2 Overview

Within the Tutorial song, you will see the following onscreen:



- 1 Transport field** This is where you control the operation of Logic. You can turn on Cycle, set drop in/out points for recording, adjust synchronization settings, and many other options.
- 2 Main menu bar** This is where you will find global functions, e.g. for saving and loading songs or for opening various windows.
- 3 Bar/Beat Ruler** The Bar Ruler displays Logic's time axis. Here, you can set markers with the mouse, or jump to any desired place in a song.
- 4 Arrange area, with sequences** A track may contain any number of sequences. Sequences contain the actual data, such as notes, controller data, etc. The data can be edited in a variety of ways.
- 5 Telescopes** If you click on the telescopes, you can alter the magnification factor of the window's contents and adapt them to your screen resolution.
- 6 Transport window** The transport window performs the same functions as the transport field, but can be located anywhere onscreen and is variable in size. A "slider" enables quick jumps to any song position.
- 7 Track List column** Here, you can determine the MIDI channel for each track, swap, insert or delete tracks.

8 Toolbox *Using tools from this box enable you to edit sequences, notes or other data in a variety of ways.*

9 Sequence parameter box *The sequence parameter box is where quantization, transposition and other aspects of the playback for a sequence can be non-destructively edited.*

As you can see, the Arrange window is divided into three basic “areas”—from left to right, these are; the Parameters, the Track List and the Arrange area. Above the Arrange area, you’ll find the Bar/Beat Ruler, sometimes referred to as the Time Line.


While reading the information in this section, you’ll learn how these various areas interact with each other and will also discover how similar the handling of both MIDI sequences and audio regions is in Logic.

3.3 Tracks and Sequences


Like a multitrack tape machine, Logic works on the basis of “tracks”. You can see and access these tracks in the Arrange window’s Track List—shown alongside.

Narrow rectangles known as “sequences” appear in the *Arrange Area*—horizontally aligned with the tracks listed in the Track List. A sequence represents an individual recording, or “take” of MIDI data. Each time you record, a sequence will be created on the selected track. You can consider the sequence a “container” for the actual MIDI data. This data can include—either individually or in combination—note events, control data, program changes, or even sysex data for your MIDI tone generators. To explain;

- Note data are derived from the notes being played on your MIDI keyboard. It includes information about the time (bar/beat position) the note was played, how long the note was held and the velocity at which (how fast) the key was struck.
- Control data (continuous controllers) includes volume and pan position settings and changes, plus any other controllers that you may use and that your synthesizer responds to.



- Program changes allow you to select different sounds (or “patches”) from your MIDI synthesizer or soundcard.
- Sysex (short for system exclusive) is a part of the MIDI language which can be used to store the entire memory of your MIDI devices, amongst other things.



Tracks with sequences

Information Track and Instruments

Take a closer look at the Tutorial song’s “information track”.

On track 1, you can see the “A intro”, “B groove”, and subsequent sequence objects. “No Output” is displayed in the track column of track 1. This is a “dummy track”, which is not routed to a MIDI output port. The sequences on this track do not contain any MIDI notes or other information. They are simply used as reference markers for the various song parts. As you continue to work through the chapter, you will be using this “information track” as a reference.

Instruments for the Tutorial song are found on the remainder of the tracks: piano on track 2, bass on track 3, guitar on track 4, and so forth. The MIDI channel used by each track is visible in the track parameters box. This information will update as tracks are individually selected in the Track List. In addition, an icon can be displayed for each track. This visually indicates the type of instrument in use and can be freely changed.

3.4 The Arrange Window


As mentioned, the Arrange window is divided into three areas. This section of the Introduction Manual will give you an overview of the Arrange window's *interface*.

Parameters Area

There are three “boxes” in the parameters area. They are, from top to bottom, the MIDI Sequence/Audio Region parameters, the Tool Box and the Track/Instrument parameters.

Sequence/Audio Region Parameters

This parameter box, also known as the *Object Parameters Box*, is directly related to the MIDI sequences and audio regions which appear as rectangles in the *Arrange Area* to the right of the *Track List*. When either a MIDI sequence or audio region is selected—by clicking *once* on it with the mouse—this parameter box will update to reflect the parameters assigned to that particular sequence/region. Give it a try on several sequences, and pay attention to the changes which occur in the *Object Parameters Box*.




Each “object” in the *Arrange Area* may have its own parameter settings, allowing independent transposition, quantization and more. The parameters available for MIDI sequences and audio regions are different. The reasons for these parameter differences are due to the very nature of MIDI and audio, which we discussed in the first chapter of the Introduction Manual.

To change a parameter value, simply click-hold to the extreme right of the parameters box—alongside the parameter entry. This will open a flip menu for some parameters, and for others will change the cursor to act as a slider. For these parameters, drag the mouse on the vertical axis (up and down) to change the value. Please select a sequence, and give this a try for each of the parameters to familiarize yourself with the methods used to interact with each of them.

Some Extra Tips for the Object Parameters

Tip

- In the Object Parameters box, the transpose, dynamics, gate time & delay functions have a couple of “zones” to the right of the text where you can click with your mouse. If you click to the extreme right of the box, you will be able to increment/decrement values in individual steps. If you click the mouse in about a half centimeter from the right hand edge of the parameter box **Delay**, a flip menu of mathematical variables will show up—**1/8th**, **1/16th** a.s.o.—allowing you to select one, if appropriate to the task at hand. Why not give it a try?
- On a program-wide level. Double-clicking on numerical values in almost all parameter boxes, editors, on the transport bar etc. will allow you to directly type in a value. This method of direct numerical entry can be used for quantize, program changes, many effects parameters etc. which will accelerate your workflow. To do this, double-click on the numerical values within the various parameter fields and use your computer keyboard to type in a new value, followed by the  key. Once again ... give it a try.

It should be noted that the Object parameters are available as real-time processes, meaning that changing these parameter values—quantize, transpose etc.—can occur while Logic is running. These processes occur on *playback* and do not actually alter the underlying MIDI data. To undo any changes made to an object’s parameters, simply select the appropriate object, and change the parameters back to their former settings using the techniques described above.


Important!


The Tool Box

Key to selecting and altering MIDI and audio information in the Arrange Window and Logic’s other editing windows, is the Toolbox. This contains a pointer, pencil, eraser, scissors & glue tools plus others which allow you to select, draw, cut, copy, paste, delete, merge and crossfade (audio regions only) sequence and/or audio regions. There is also an automation “draw” tool.



The toolbox is context-sensitive. This means: Its look depends on the edit window. Different tools will appear for particular tasks in the various individual edit windows. As an example, there is no crossfade tool in the Score window as audio is not handled in this editor. There is, however, a voice separation tool in the Score window. The practical use of the tools is discussed throughout this chapter.

In the toolbox, you can select any editing tool required by simply clicking on it with the mouse. You can also select a second tool for use via  + mouse button on Mac OS.

When you need to use any of the tools, hit  on your computer's keyboard and the Toolbox will “float” at the location your mouse pointer currently occupies onscreen. When the floating toolbox appears, simply select the appropriate tool with your mouse cursor. As usual, try it out.

Tip



The Track/Instrument Parameters

This set of parameters is linked to the second onscreen area—the Track List—and is used for global parameters such as the selection of instruments (**Prg**—Program Change), the overall track volume, transposition and more for *all* “objects” on the track.

This parameter box will update each time a new track is selected in the Track List.

Please select a few tracks in the Track List with the mouse or by using the *up/down arrow* keys on your computer keyboard. While doing so, watch the changes in the Track/Instrument parameters box.



The Track List

The second area of the Arrange window is known as the Track List. This is where you can add, delete, select, name and reorganize the tracks/instruments used in your song.

Note the highlighted track in the list. This (or any) MIDI track is automatically “armed” for recording—indicated by the red **R** button—as soon as the track is selected. Any MIDI input received by Logic, when in record mode, will be recorded to this track. This recording will then appear as a sequence in the Arrange area.

The illuminated **M** on track 11—“Grand Piano”—indicates that all objects on the track are muted—i.e. all objects aligned horizontally on this track are silent. The mute button actually stops MIDI data transmission on the track.

The (orange) indicator you see to the left of track 12—“Fingered Bass” is a level/activity meter. Such meters appear on all active tracks and are useful aids for keeping an eye on what tracks contain objects that are *currently playing* and their relative levels.

Recording *audio* tracks is a little different to that of MIDI tracks. Audio tracks must first be “armed”, which is achieved by clicking on the **R** button on the desired track (You can also customize the *Record Enable Track* Key Command). Once armed, pressing the **Record** button on the Transport Bar will start recording audio data to the selected track.


N.B.—Before *any* audio can be recorded, you must first set a recording path and file name—i.e. a location on your computer’s hard disk and a name for your audio files. We’ll take a look at how to do this shortly.

Muting/unmuting of MIDI or audio tracks is achieved by clicking the **M** button on each track in the Track List or by use of the **[X]** Key Command on a *selected* track. Give both a try.




Reorganizing Your Tracks

You may want to reorganize your tracks to keep things neat onscreen, or to group audio tracks or particular instruments together, which can be useful for scoring. To do this, move your mouse pointer over the *number* on the track you wish to move, and click-hold the mouse button. This will change the appearance of the cursor to a “hand” icon as shown.





With the mouse button held down, drag the track up or down the Track List to the desired location, then release the mouse button. This will change your track order, and will also move all of the associated Track objects—sequences or audio regions—in the Arrange area. Please try it out.

The Arrange Area



The third area of the Arrange window’s interface is the large gray *Arrange Area*. This is where your audio regions and MIDI sequences are “arranged” into a song. You can freely drag and drop your audio and MIDI “objects” from position to position, make loops, copies and more.

Audio and MIDI data can be recorded directly into the Arrange area as mentioned earlier.

You can add audio regions—in either WAV or AIF format (or SDII format on Mac)—directly to the Arrange area by drag and dropping them from any folder on your hard disk. Another method for adding audio regions to the Arrange window is by pressing   while clicking at the desired location. You can also mix your audio and MIDI objects directly in the Arrange area, which we'll discuss in the next chapter.

Above the Arrange area, you'll see the *Bar/Beat Ruler*. This is used for a number of functions performed in the Arrange area, including song navigation. Much of the Bar/Beat ruler's functionality is tied to the Transport Bar, which we'll discuss now.

Reload the original Tutorial Song now, if you have made any changes to the sequence parameters, track order etc.

3.5 Navigating the Song

In this section, you will learn how to move to different parts of the song, start and limit passages, and to isolate and audition specific portions and components within the song—in short, you'll learn how to “navigate” through the song. As you're reading, follow the steps and try out the functions. You can't “break” anything.

The Transport Bar

The second, smaller window, displayed after loading the song is the floating Transport window. It is laid out like the control surface of a tape machine, with the top row of buttons used for operating the **Record, Pause, Play, Stop, Rewind and Fast Forward** functions. In addition, you can use the Transport window to change the tempo settings and engage operations such as *solo*, *synchronization*, or *cycle* which we'll cover shortly.



You can start the song by clicking on the **Play** button on the Transport bar, or by pressing **[enter]** on your numeric keypad.

You may hear that the song is not completely arranged, and contains a few inconsistencies. As you continue to work through this chapter, you will finish arranging the song, add a few details, and correct one or two mistakes that we intentionally left in. Following this, the song will be completed with the addition of some audio files.

Try out the buttons in the upper row of the Transport bar. You should be pretty familiar with them as they are identical to the functions found on tape machines and cassette recorders. Each function has a Key Command, as discussed in the first chapter.




Moving to Different Song Positions

There are several ways to “jump” to specific song positions.

At the top of the Arrange window, you can see the Bar Ruler.




- Click at various spots in the lower half of this ruler and you’ll immediately “jump” to that position. As you click, a vertical gray line will appear in the Arrange area aligned with the point selected on the Bar Ruler. This is the *Song Position Line* (SPL) which, in the most general sense, is comparable with the tape position indicator on a traditional recording device.
- Engage **Play** via the Transport Bar or .






- Now click on the Bar Ruler, and hold down the mouse button. Take note of the SPL, which moves to align itself with the mouse position in the Bar Ruler. You can move to any position in the Bar Ruler, and audition different sections of your song instantly, by moving the SPL in this way. **Play** *must* be engaged for this live “auditioning” (i.e. hearing) to occur.



If you would like to “jump” directly to a specific position when the sequencer is not in play mode (press the **Stop** button now, if Logic is presently running), you can also take advantage of Logic’s “locators”. To the right of the transport buttons, the current song position—in both absolute time (that’s hours, minutes, seconds, in plain language) and as musical measures (bars/beats etc.)—is displayed.



- Click-hold on the song position indicator, and with the mouse button depressed, drag the mouse on the vertical axis (up and down) until the song position displays “17 1 1 1”, and start playback—you know the Key Command. Logic will begin playing at measure 17. Take note of the SPL as you’re doing so.
- Another way of doing the same thing is to double click on the current song position locator on the Transport bar. This will open a text dialog box, where you can directly type in **17 1 1 1**. Give it a try.



It is essential that you type **17** and then press the space bar () , then **1**, and then the , and so on. Once all numbers have been entered, just press the  key. If the space is not added between numerical values, Logic will interpret this as bar 17, 111 and will ignore your entry, as it exceeds the song length.

As a great shortcut, you can simply type in **17** and then press the  key when you want to jump directly to the *beginning* of a bar. If you want to go to any position *other than the first beat* in any bar, you must include all 4 numerical positions. As an example, **17 3 2 2** (don’t forget the ) , which translates to bar 17, beat 3, sub-beat 2, clock tick 2.

Tip

Display Current Song Position

If you manually enter and jump to positions, the song overview displayed can, on occasion, not correspond to what you hear. You can, however, guarantee that these two things always match.

- Click on the **Catch** button found to the upper left of the Arrange window, and the song overview will update, following the song position line again.

This facility ensures that when the song position line exits the visible portion of the song overview, the display will update to follow it. In general, catch mode should be activated while using the program.

Zoom a Window Excerpt

You can view the entire song in the visible portion of the window by using the telescope symbols at the top right.




Click on the left half (narrowly spaced lines) of the telescopes until you can see all of the sequences in the window. For both platforms, there are also Key Commands for zooming, which we discussed in the *Zooming* section, from page 35 onwards.



Give it a try!

Cycle Mode

In cycle mode, you can endlessly repeat a section of the song as long as **Play** is engaged. This is useful for editing sequence parts “live”—i.e. as the song is playing, or for the recording of new tracks to a specific section of the song. Two “locators” can be used for setting *cycle regions*. These are position markers that define the left and right boundaries of a song segment. They are found directly to the right of the *bottom row* of the Transport’s control buttons.



To activate Logic's cycle functions:


- Turn on the cycle mode by clicking on the **Cycle** button in the Transport window or by pressing the cycle Key Command—[C]. When active, the cycle button will turn green.



In this example, we'll use part "C" in the information track as the basis for setting the cycle region boundaries.

- If necessary, use the horizontal scroll bar (by click-holding and dragging left or right) at the bottom of the Arrange window to scroll the window view, until you can see sequence "C".
- Click on this sequence once, which will turn black, indicating that it is selected.

In the **Functions > Object** menu, select **Set Locators by Objects**. This will create cycle region boundaries which match the size and position of sequence "C's" left and right boundaries. Pay particular attention to the display changes that occur in the *Bar Ruler* at the top of the Arrange window:



This visual representation of the cycle region (the highlighted section) can be interacted with directly in the Bar Ruler.

You can adjust it in the following ways:

- Move it by grabbing it in the middle and dragging your mouse to the left or right.
- You can also change the region borders by grabbing either the bottom left or right corners of the highlighted section on the Bar Ruler, and moving the mouse left or right.

Try both and when done, resize to match the region shown. Press **Play** and allow the region to cycle over the selected 8 bar section. You can even resize the cycle region while the cycle is playing, using the technique mentioned above. When cycle mode is engaged, pressing **Stop** twice will move the SPL to the beginning of the cycle region, rather than the beginning of the song, which is its default behavior. Give it a try.


Selection Techniques


In order to edit *any* data type in Logic—be it sequences, audio regions or notes—you first need to select them. All functions and operations will only affect items that are *selected*.

Solo

- To start, turn on the solo function by clicking on the **Solo** button in the Transport window or by pressing **[S]**—the *Solo* Key Command. The **Solo** button and the Bar Ruler at the top of the Arrange window will turn yellow.
- Ensure that “Cycle” mode is also enabled, and that the cycle region boundaries extend from bar 25 through 33 (Section “C”).
- Start playback, and click once on the “Piano C” sequence to highlight it. As mentioned earlier, highlighted sequences will turn black indicating that they are selected. You will hear the piano part in isolation, because when **Solo** is active, only selected sequences will play.
- Click on the other sequences in section C, one at a time, to “solo” them.
- Once you’ve got the hang of this, you can go one step further by “soloing” several *selected* sequences.
- Select “Piano C” once more.
- Now, hold the **[⌘]** key down, and click on the “Bass C” sequence. This will also be selected and played.
- With the **[⌘]** key still depressed, click on the “Groove Real-time” sequence. You should now hear the piano, bass, and percussion parts.



- While still pressing the  button, click just below the “Groove Real-time” sequence, and keep the mouse button depressed. Now, drag a “lasso” over *all* of the sequences in section C.
- Your previous selection will now be reversed and you will hear all sequences *except for* piano, bass and percussion.

Try out the selection functions with other sequences, individually and grouped (using the  key), if you’d like more practice.

And congratulations!

You’ve just mastered the most essential of Logic’s techniques—the selection of objects—sequences, notes, audio regions ... you name it!

3.6 Changing and Creating Sequences

Although we briefly touched on the Object Parameters in the *Parameters Area* section, from page 121 onwards, and the Tools elsewhere, this portion of the Introduction Manual is altogether more in-depth and hands-on. You will learn most of the *practical* information you need to handle sequences in this section, so take your time. Practice each step as many times as you need to.

Quantize

Quantizing is the rhythmic correction of notes, aligned to positions on a “grid”. When quantization is applied to any selected event or sequence, Logic will move all note events to align perfectly with the nearest grid positions.

1	2	3	4	1	2	3	4

In the image, the first 4 beats show unquantized note events. In the second four beats, the notes have been quantized, and now align to the nearest beat positions on the “grid”.

We’ll use the “Groove Real-time” sequence as an example. The timing of note data in this sequence was intentionally left slightly off the beat. To correct these small timing errors, you will use Logic’s quantization facilities.

To best illustrate how quantization affects MIDI note timing, we strongly recommend that you enable the Metronome.

- To do this, click on the **Metronome** button found towards the lower right of the Transport bar.



By default, Logic transmits the metronome click to channel 10 of the first available MIDI port. Ensure that your tone generator (preferably a GM device) is connected to this port, or set up a metronome as per the instructions in the *Creating the Metronome Object* section, from page 77 onwards.

Press **Play** and solo the drum sequence, using the technique you learned earlier. When compared to the metronome click, you will hear that the “groove” is not perfectly on the beat.

- In the *Object Parameters* box, click-hold on the **off (3840)** text alongside the **Qua** entry. In the flip menu which opens, select the **16D Swing** setting, and release the mouse button. This quantize value will then be displayed in the sequence’s parameter box. As the sequence continues to play, you’ll discover that it now sounds rhythmically perfect.
- Try out the other quantize values on this sequence, in order to hear the effects of Logic’s quantizing options. Once you’re done, reselect the **16D Swing** setting.

Spend some time looking at the quantize settings used on the various song parts. Remember that selecting each sequence will update the Object Parameters box.

You will notice that the swing factors—Quantize values followed by an alphabetic character—are different for many of the sequences. Judicious use of these “groove” factors can make your choruses sound like they “swing” more than verses do, for example. This is a great thing because your music will sound like it’s played by you, rather than your computer, even if the quantize functions are used.

Another thing to consider, while experimenting with different quantize settings, is that this operation happens in real-time, while the sequencer is playing. As you’ve also discovered, you can jump to different song positions, solo tracks and change cycle regions while Logic is playing. This real-time functionality is available for most Logic operations and allows you to concentrate on your music, not wait for the program to process data, while listening. Keep reading, there are many other real-time features and functions for you to discover which will aid your creative flow.

Loops

“Loops” are automatic repetitions of a sequence. The loop function enables you to repeat a passage as many times as you wish, without having to copy it.


Let’s add a cabasa to the Tutorial song. We’ll use it in the “B Theme” and “Groove” sections of the song, as outlined in the information track.

A sequence named “cabasa” can be found on track 10 at the beginning of bar 17. You will notice that it is muted. Muted sequences are identified by an asterisk which precedes the sequence name, and are also paler in color than non-muted sequences.



- Click on the sequence *once* with the mute tool, which will unmute, and select it.
- Click once with the mouse alongside the **Loop** entry in the Sequence Parameters box. This will then display the word **ON** to indicate that the loop function is active.

You should now see the following displayed onscreen:



The cabasa sequence will now be repeated until the end of the song is reached. In this example, however, we'd like to stop it before then. Loop repetitions are displayed as gray bars that are of the same length as the original sequence.

The way the loop function works is as follows:

A looped sequence is repeated until it encounters another sequence on the same track (or the song ends). To “turn off” the cabasa at a desired position, simply insert an empty sequence onto the cabasa track. For now, we'd like you to do this at the beginning of section C. Here's how ...

- Select the **Pencil** tool from the toolbox, and click once in the cabasa track at position 25 1 1 1—i.e. directly on top of the loop repeats. This will insert a new, empty sequence and your screen should now look like this:




The insertion of this blank sequence onto the cabasa track will stop the looped cabasa part at measure 25. Press **[esc]** twice.

Copying a Loop

As a final step for you to try with this loop example, we'd like you to copy the cabasa part to the “groove” section of the song.

- While pressing the **[⌘]** key, click on the cabasa sequence, and—*importantly*—the “stop” sequence you just inserted. When both have been selected, release the **[⌘]** key.


- Press the  key. Click on the cabasa sequence, and drag the entire section to measure 33, while keeping the modifier key pressed. The entire passage, including the stop sequence, will be copied, and you're done!

If the “stop” sequence is not copied, the original sequence—with the **Loop** playback parameter active—will be copied to the desired location. This will create a sequence copy with loop repetitions that continue to the song end point, which may not be what you want to happen.

The **Loop** parameter, and the **Copy** function that you just used are a great way to quickly create drum tracks, bass parts etc. that are repeated throughout your songs. In many musical styles, the use of recurring motifs (the same bassline, drum part, chorus etc.) is commonplace, and you now know this technique which may help you to arrange your future songs more quickly and easily.

Resizing a Sequence

Each sequence (or audio region) can be resized by clicking on its bottom left or right hand corner and dragging to the left or right.

-  With audio regions, dragging from the bottom left hand corner to the right will also move the anchor point, which we'll discuss later in the chapter. Dragging from the right hand corner to the left will shorten the audio region. No audio region can be longer than the underlying audio file on which it is based.

The reason why you would want to resize any sequence or audio region may be to create a drum “fill”, or simply a variation on an existing sequence (or copy). Perhaps a section of a solo?

- Using the looped cabasa section—*not* its loop repetitions—you just created, click and hold on the bottom right-hand corner and adjust its size by dragging the mouse left or right.

- As you can see, the cabasa sequence and all of its loop repetitions have changed length. Now play the sequence (and loop repetitions) to hear the differences.
- This is a real time function, so why not set up a cycle region over this section and resize a few other sequences to see how using a portion of some parts, and lengthening others, can completely change your arrangement?

This functionality, combined with the looping and copying functions is a great creative tool that can help with quick song construction.

While experimenting, ensure that any changes you make to your sequence lengths are returned to their original state.

Moving a Sequence

Using the mouse **Arrow**—the “default” tool—you can move sequences onto other tracks, or to other positions within the Arrange window.

To illustrate this, we’ll insert a “B” part in front of the groove section of the Tutorial song. From there, we’ll transpose this newly created B section by a semitone. Before beginning, however, we need to create some room in the arrangement to accommodate this new section. Here’s how:

- Press the mouse button and rubber-band select all of the groove section sequences.
- Once all are highlighted, grab and drag them eight measures (bars) to the right.
- Use the position display on the Info Line as a reference point. It should read “41 1 1 1” when you release the mouse button.


As part of your general working method, you should *always* refer to the Info Line when carrying out any of the following operations in Logic: move, copy or cut/divide. This will help you when editing and arranging, and can aid in avoiding disastrous mistakes. See the Undo section below.

Tip

- The Info Line appears at the top of the active edit window, whenever you are performing an edit.

Divide 3 3 1 1 Seq 7 8 1 0 0

Once you're done, the Arrange area should look like this:



Undo/Redo

Did you make a mistake, like not selecting all of the sequences, or perhaps you moved them to the wrong place?

If so, this is a good time to become acquainted with one of the most important functions in Logic—the “Undo”. With the *Undo* function, you can always undo the last *editing* step, should things go wrong.

- To use the *Undo* function, select **Edit > Undo**. In this example, the sequences will be reset to their original positions and you can now re-attempt your edit. Give it a try, even if you got the edit right.
- To reverse the *Undo*, select **Edit > Undo** a second time.




It's important that you make the distinction between what can be undone and what can't. As an example of this—the quantize or transpose playback parameters do not actually alter data. They simply change the way it is *played back*.

Important!

Real-time playback parameters such as these do not involve an *edit* operation, and therefore the *Undo* function has no effect on them. As covered earlier, to undo a playback parameter, simply select the affected sequence, and adjust/reset the appropriate parameter to its former (or default) value.

Copying Sequences

Following the repositioning of the “groove” section and the creation of the blank measures between bars 33 and 41, it’s time to insert our “B” part.

- Rather than recording an entirely new section (don’t worry we’ll get to that shortly), you will now copy the “B groove” section to the empty area created when we moved the “groove” section.
- Rubber-band select the sequences of the “B groove” section and release the mouse button.
- Press and hold  and click-hold on *any* of the selected sequences and move the mouse to the right. A copy of all selected sequences is now dragged with the mouse pointer. (As you’re dragging, you will see a “ghost” outline appear)
- Drag these sequence copies to measure “33 1 1 1” (keep an eye on the Info Line) and release the mouse button, where they will fill the space left when you moved the “groove” section. These newly created sequences will have the names of the originals, with the text “*copied” appended to the end of the name.

You can decide whether or not this extension should appear in the sequence’s name by opening the **Options > Settings > Global Preferences** dialog. Click in the checkbox to the left of the Add Last Edit Function to Sequence Name option if you want a description of any edit operations to appear on edited sequences. If not, uncheck the box.

Tip


Cutting Sequences

Now, let's cut the sequences in the section just copied in half, using the **Scissors** tool. Following this, we'll take a look at the **Transpose** function.

- Rubber-band select the sequences that were just copied.
- Select the Scissors tool by clicking the scissors symbol in the toolbox. This will change the appearance of the mouse pointer to that of a pair of scissors.
- Click on one of the selected sequences, while holding the mouse button down, and move the mouse left or right. While doing so, constantly refer to the information line.
- When position “37 1 1” is reached, release the mouse button. This will cut the selected sequences at the beginning of bar 37.

Transposing Sequences

Reselect the **Arrow** tool, and rubber-band select the sequences between measures 37 and 41. We will now transpose this half of the newly created “B” section, while leaving the first half in the original key. Transposition is the changing of the pitch of a MIDI event or sequence by a number of semitones.

 There are two semitones to every tone. There are twelve notes in the Chromatic scale, which use the letters A, B, C, D, E, F and G. The other five notes of the Chromatic scale (A#/Bb, C#/Db, D#/Eb, F#/Gb and G#/Ab) are named by placing a sharp (#) symbol after a note letter to make it one semitone higher, or by placing a flat (b) symbol after a note letter to make it one semitone lower. Transposition makes the selected note/sequence play back higher (sharp) or lower (flat) in the Chromatic scale.

Take a look at the **Transpose** parameter in the Sequence Parameter box. It contains an asterisk (*). This means that the selected sequences each have different transposition values. A nice feature of Logic is that global adjustments made to

Transpose *

multiple sequences work relatively. In other words, this means that individual transposition differences (the relative pitches) between sequences are maintained, even if all sequences are transposed.

Let's get on with the job.

- Click on the asterisk that appears alongside the **Transpose** parameter in the Sequence Parameters Box, and with mouse button depressed, move the mouse upwards until the value **+ 1** is displayed.
- Release the mouse button. The passage has now been transposed up a semitone. A value of **+2** would transpose by a tone.

Move the song position line to measure 37, press play, and listen to the result.

You'll hear that this transposed section doesn't sound particularly good, and that some fine-tuning is required. Here's what went wrong.

The percussion part will sound somewhat strange. This is because you unknowingly transposed the percussion sequences, causing the drum note placement to shift. You will need to undo the transposition for the percussion tracks. To do so, select the drum sequences, and drag the **+1** transpose setting down, until the line is empty. This indicates no transposition.

Another problem is that the bass in the copied, and cut B-section, which we have transposed (between bars 37 and 41) is a loop repeat, not a "real" sequence copy.

Loop repeats are merely pointers to the original sequence and can *not* be transposed. Only a "real" sequence or a copy may be transposed. In order to transpose the bass part, you will need to change the loop repeat into a real sequence.

Important!

- Select the "Bass theme*copied" sequence in this section.


- Choose **Functions > Turn Loops to Real Copies**. A new sequence will now replace the gray loop repeat.
- **Transpose** this up one semitone, from **–12** to **–11** and your transposed section, between bars 37 and 41, will now be perfect.



Your First Recording

The final MIDI exercise in the Arrange window is to make your first recording. Rather than starting a new song from scratch, you can play a solo over the C-section. A flute solo is already in this section, but it could almost certainly be replaced by a better one.

As you're new to using Logic, you may not play the solo perfectly on your first attempt. To aid you in this regard, plus introduce you to a nice Logic feature, we'll set things up so that you can record several "takes" automatically. Once you've finished recording, you can then select your favorite version of the solo.

- **Step One:** Delete the existing solo. Select the **Eraser** from the toolbox and click on the "flute" sequence, or select the sequence with the **Arrow** tool and press . It will be deleted.



Now set the cycle and record parameters. You'll probably want a bit of a lead in, before the solo starts, to ready yourself for playing. We therefore suggest that you extend the cycle region's start point (remember the left corner drag discussed in the *Cycle Mode* section, from page 129 onwards) to be longer than the actual recording—i.e. from **23 1 1 1** to **33 1 1 1**. This will give you two extra measures before section C commences at measure 25.

We're sure that you don't want to manually start and stop recording with every cycle region repeat and, thankfully, you don't need to. Logic offers the "Autodrop" function which engages and disengages **Record** automatically at predefined points (this is often called "Punch In/Out"). To do so:

- Click on the **Autodrop** button in the Transport window, just to the right of the **Cycle** button—or use the Key Command. On doing so, the *Bar Ruler* will divide into two sections. The Autodrop bar appears just below the cycle region. Adjustment to the left and right ends is as per the cycle region.




- Set this to span bars 25 through 33, as shown above.


Song Settings

For the next step, a few settings need to be changed.

- Open the **Options > Settings > Recording Options** window.
- Check the **Auto Mute in Cycle Record** box.



Selecting this setting causes each previous take to be automatically muted when the cycle repeats. This way, you can record one passage after another, without being distracted by (i.e. hearing) your previous takes. If you would like to hear the

metronome while recording, you should enable **MIDI Click** now. The metronome is sent on channel 10—the drum channel—of the first available MIDI port. Confirm the changes to the **Auto Mute in Cycle Record** option by clicking the **OK** button or .

Let's Record!

- Select track 8 on the Track List—the one with the small flute icon—by clicking on it. Simply selecting the track will “arm” it for recording.
- You can now play the flute sound from your MIDI keyboard.
- You can also select other tracks to try them out—Logic automatically addresses the right instrument (*MIDITHRU*). Finally, switch back to track 8.


To have a few practice runs, you can simply start playing the cycle and do a little experimenting on the keyboard while listening.

If you find soloing in E major is difficult, you can **Transpose** the *MIDITHRU* four semitones down (-4) to C major. If you're unfamiliar with musical keys like “C major”, transposing the *MIDITHRU* as suggested will allow you to play any of the white notes on your keyboard, and this should sound OK ... i.e. “in key”.

Tip

MIDITHRU always appears in place of a sequence name in the Sequence Parameters Box, when no sequence (i.e. anywhere on the gray background) is selected in the Arrange window.

Any changes made to the settings of the *MIDITHRU*, in the Sequence Parameters box, will be applied to any subsequently recorded sequences.




- When you're confident enough to record the solo, begin recording by clicking  on the numeric keypad, or by pressing the **Record** button on the Transport bar. As usual, we recommend the use of the Key Command.



The count-in of two measures will play through, and the cycle region will begin to play repeatedly. You can play over the first two measures of the cycle region, until Logic reaches the left Autodrop point (measure 25) in the song. Anything you play from measure 25 onwards will be recorded. At measure 33, recording will automatically stop, and a sequence will be created on the selected track.


- Allow Logic to continue running. After reaching the right cycle region boundary (measure 33), the SPL will jump back to the left cycle region boundary (measure 23). At measure 25, the next recording will begin.

Allow the section to repeat, recording on each pass, until you feel that you have one or two good “takes”. Logic will create a new track automatically, for every cycle repeat, and will move previously recorded tracks down the list.

- Using the **Mute** tool, you can now audition the individual takes. 
- Once you’ve decided on a take, simply delete the unwanted takes by clicking on the corresponding track(s) in the track column. Once selected, use the **Functions > Track > Delete Track** menu function repeatedly, until all unwanted tracks are removed. 
- If you accidentally delete the good take, don’t forget the **Undo** function. 

Saving the Song

Here’s how to save the Tutorial song, with your new solo:

- Choose **File > Save As...**, and enter a new name—i.e. NOT “tutorial”—for the song to be “saved as” in the ensuing file dialog. 


Reload the original Tutorial song for these additional exercises.


3.7 MIDI Event Editing

This section briefly discusses the use of Logic’s various MIDI editing windows.

The Event List Editor

This editor shows all data contained within a selected sequence as an alphanumerical (a collection of numbers and letters) listing.

- Open the Event List for the “flute” sequence, via the **Windows > Event List** menu or by pressing .



25	1	3	201	PitchBd	4	6	52	
25	1	4	25	PitchBd	4	15	37	
25	1	4	97	PitchBd	4	25	19	
25	1	4	145	PitchBd	4	107	3	
25	1	4	193	PitchBd	4	0	0	
25	1	4	217	Note	9	84	127 1.232
25	2	1	49	PitchBd	4	52	3	
25	2	1	113	PitchBd	4	116	20	
25	2	1	185	PitchBd	4	29	45	
25	2	2	9	PitchBd	4	0	64	
25	2	2	233	Note	9	C5	121136
25	2	3	225	PitchBd	4	75	60	
25	2	4	49	PitchBd	4	71	34	
25	2	4	113	PitchBd	4	105	6	
25	2	4	160	PitchBd	4	0	0	


The **Status** column displays the event type. The “flute” sequence contains both note and other types of events. You can hide/show specific event types by using the *filter buttons* to the left of the list.

Click on each of the buttons, except for the one showing a slider at the bottom of its range, so that they turn dark gray.

The Event List will now only display control change events.

- Click on each button, re-enabling the display of all events. Note that as you do this, events of that type will re-appear in the list.

We will now insert two *program change* messages into the solo, changing from a flute sound in the first half, to a synthesizer sound in the second.


-  A program change message is part of the MIDI language. It tells a synthesizer or soundcard to select a particular sound or “patch”—like a flute or synthesizer sound—from a particular memory location. If you think about it in a different way, this is like telling your computer to select a particular file for copying or editing. Remember that MIDI synthesizers and sound cards are really computers in disguise, so a program change is a lot like a “select this file” now message.

As the solo begins at measure 25, we’ll place the first program change for the flute at measure 25.

- Move the song position line to bar 25 1 1 in the Arrange window. The SPL is used to determine the insert position for the program change event (message).
- Select the **Pencil** tool from the Event List’s toolbox, and click on the program change button shown to the right.



A program change event will be inserted at position 25 1 1 1.



The screenshot shows the Event List window with a yellow background. The title bar reads "nennung der Liste". The table contains three rows of data:

	25	1	1	1	Program 1	-	73	Flute
	25	1	3	201	PitchBd 4	6	52	
	25	1	4	25	PitchBd 4	15	37	

The program change number is found in the **Val** column. Set this to **73** if you own a GM tone generator. If you are not using a GM tone generator, find a program change number that selects a flute (or flute-like) sound.


Now, we’ll insert a second program change:

- Move the song position line to position **29 1 1 1**, and click on the **Program Change** button.

Choose a **Val** of **87** if using a GM tone generator, or a program change that selects a synthesizer solo sound, with non-GM devices.

- Select the **Arrow** tool from the Event List’s toolbox and use the buttons to hide all event types, except program change events.

Your event list should look like the following:



Move the SPL to the beginning of the solo sequence (position 25 1 1 1) and press **Play**. You'll hear the solo switch sounds halfway through the sequence.

Congratulations, you've mastered the insertion of program change events. The Event List is very useful for microscopic changes to your sequences. Make sure you read the chapter on it in the Reference manual.

About Program Changes

It should be noted that the Event List procedure outlined above physically writes the program change message to a MIDI sequence object on a track. The advantage of this method is that if a program change message is *written* to a sequence (or several sequences) at the beginning of (or throughout) your song file, then this information will be sent to your MIDI module or soundcard *every* time you load and play the song. This guarantees that the right sounds will be sent every time, even if the song is saved as a MIDI file, and played on another sequencer or SMF-player (Standard MIDI File Player).

As Logic is full of options which allow you to work the way you prefer ... it is also possible to send a program change event by clicking the checkbox beside the **Prg** entry and inserting a number (or scrolling through a list, with the mouse button held down) from the *Track Parameters* box in the Arrange window. You can also do the same from within the Track Mixer window via the top panel in each MIDI fader.



The problem with the latter two methods is that the Program Change message is not *written* anywhere. Even though the settings you make using either method are saved with your song file, there's no guarantee that your MIDI module or soundcard will actually "see" these messages.


If you find that you've loaded a song and your sounds aren't quite right, you should enable the **Send Used Instr. MIDI Settings after loading** checkbox in the **Options > Settings > MIDI Options**, and resave your song. Note that this must be done for all previously created songs.

If done in your Autoload song, which forms the basis of all of your future work, this will become a default preference. Once done with the Introduction Manual, don't forget to set this in your Autoload song.

Tip

The Matrix Editor



Although it looks very different, the Matrix editor is quite similar to the Arrange window. Unlike the Arrange window—note events, rather than sequences—are displayed as horizontal bars in the Matrix editor. Editing, as you'll see, is quite similar.



The “Strings C” sequence displayed in the Matrix window.

- Select the “Strings C” sequence in the Arrange window and open the Matrix window via the **Windows > Matrix** menu.

The keyboard along the left edge of the Matrix window indicates the pitch of the notes/key played in the display. A chord is represented by a group of overlapping bars. You can easily see that the note lengths of the second chord are unequal. In our example, we've included a wrong note in the 4th chord, which we'll get you to fix.

Take a look at this sequence in the Event List as well, by choosing **Windows > Open Event List** or  .



As you can see, picking up these inconsistencies in the Event List isn't quite as easy as with the Matrix editor. Close the Event List window when you're done.

When making changes in the Matrix—or any other editor in Logic—you can hear the changes you make in real-time. This is achieved by activating the **MIDI Out** button found towards the top left, in each of the editor windows. We suggest that you activate this button by clicking on it. It will be illuminated when active.


Tip



Changing Note Lengths in the Matrix Editor


- Highlight all notes in the first chord by rubber-band selecting them.
- Now, grab the lower right corner of one of the selected notes, and drag it to measure 26, so that the end of the bar (i.e. note) connects to the start of the next chord. Release the mouse button.

Any change made to the length of one note, will affect all other selected notes equally in the Matrix editor. i.e.—they will retain their relative length differences.

It is possible to override this relative length difference and force all notes to have the same *end* point by pressing  while dragging the right corner of selected note events. This method will even work on note events selected across multiple bars.

Tip

- Repeat the process, to lengthen each chord so that it meets the beginning of the next. This will create a *legato* effect (where the end of one note meets the beginning of the next) on playback. Increase the zoom level to aid in the editing of the events.

You can also adjust the *start* point of any selected note(s) by click-hold and dragging the bottom left corner. Note that the  function used to align the end of notes does not work on the beginning of notes.

Tip

Changing Note Event Pitches in the Matrix Editor


- Select the **Arrow** tool from the Toolbox.
- Select any note event, or group of notes, by rubber-band selecting them.
- Grab the note(s) in the middle and drag it/them up or down. As you do so, you will hear the pitch change.
- When the desired pitch is reached, release the mouse button.

Deleting Note Events in the Matrix Editor

Now it's time to get rid of that wrong note.



- Select the **Eraser** from the toolbox, and click on the short note at position 28 1 1. The note will disappear.

As an alternative method for deletion of the note—or any other selected event—simply press .

Tip

Changing Note Velocities in the Matrix Editor

Velocities (i.e. how fast the note was hit—and usually how loud it is) of notes are indicated by color—with “hot” colors, such as reds used for higher values and “cool” colors, such as blues used for lower velocities. A further indicator of velocities is the line within the note event “bar”. Velocities of selected note events can be adjusted with the **Velocity** tool. To do so;


- Select the **Velocity** tool from the toolbox, as shown.
- Click-hold on the top note in any of the chords and drag the mouse up and down. As you do so, you'll note that the color of the selected note event changes and the line within the note changes length. Ensure that the velocity of the selected note is different to that of the other notes in the chord.
- Release the mouse button and—with the **Velocity** tool still selected—rubber-band select all notes in a chord. Once all are selected, release the mouse button.



- Click-hold on any of the selected notes and drag the mouse up and down. As you do so, you'll see that the velocity of the note that you edited individually retains its relative distance (level) from the other selected events. As you drag the mouse up and down, you'll discover that when maximum or minimum values are reached for *any* of the selected events, no further increase or decrease in value is possible.

Using HyperDraw in the Matrix Editor

In all versions of Logic, you can make volume and panning changes using the HyperDraw function, within the Matrix and Score editors. The Platinum and Gold versions also allow the “drawing” of controller curves for other types of continuous controllers.



Matrix window with HyperDraw volume curve.

To access the HyperDraw function within the Matrix editor, select **View > HyperDraw > Volume** (or **Pan** or other controller).

As an alternative method, you can press **[F7]** to show the Volume Hyperdraw. **[F4]** will toggle back to the standard Matrix editor view.

Tip


Congratulations, you've now completed the edits for the strings sequence. Nearly all sequences in the Tutorial song contain slight mistakes, which you can easily repair in the Matrix editor. Select one or two of the other sequences and edit them as you did with the String part.

You will probably notice a big difference when optimizing the lengths of notes in the bass sequences.

Tip

The Hyper Editor

This editor is useful as a drum “grid” editor, and also for graphical controller “drawing”. When used for drum editing, it is somewhat similar to the use of pattern-based drum machines of yesteryear.



The HyperEdit window

To insert note or controller information:

- Select the **Pencil** tool and click, or click and drag horizontally with your mouse. Higher note velocities/controller values appear as taller vertical bars.

To adjust existing note or controller information:

- Click on an individual event and drag vertically with your mouse (this can be done with the **Pencil** or **Arrow** tools). Alternately, you can “draw” over the existing curve.
- Select the “groove basic” sequence, and open the HyperEdit window via the **Windows** menu, or by pressing the **⌘5** Key Command and experiment with these techniques, making use of each of the tools.
- While in the HyperEdit window, click hold on the **MIDI Controls** flip menu and select GM Drum Kit. You’ll see a very different view of the “groove basic” drum part. Once again, please experiment with the various tools on the individual parts.



The Transform Window

In the last chapter, we briefly looked at the Transform objects available in the Environment. The Transform window differs from the Environment Transformers in the following ways.

- It is not a realtime process
- You can define **Conditions** by length and position.

The Transform window is a very powerful editor that can be customized to build your own preset “transform” operations. It can be used for dramatic MIDI data changes, or for subtle alterations. As an example of the latter, it could be used to reduce the amount of filter modulation from a value ranging between **97** and **105**, by a fixed percentage. While this type of change could be performed in other editors, it would need to be done on each individual modulation event. The Transform window allows you to quickly achieve the same result on multiple events.

To best illustrate how the Transform window can be used, please select the “Piano theme 1” sequence.

- Create a cycle region from bar 9 to bar 17 using the techniques you learned earlier.
- Solo the “Piano theme 1” sequence
- Open the Transform window via the **Windows** menu or by pressing  .
- Select the **Reverse Pitch** preset from the flip menu, to the top left of the Transform window.
- Press the **Play** button on the Transport and listen through a couple of times.
- While the sequence is cycling, press the **Select and Operate** button and listen to the results.
- Use the **Undo** function to return the sequence to it’s former state.
- Please experiment with the other presets and buttons, ensuring that you **Undo** between each process.

The Notation (Score) Editor

A detailed Scoring Tutorial is available in electronic form on your Logic program CD-ROM. This tutorial is accompanied by additional song material, also located on the CD-ROM.

3.8 Audio Tracks and Regions

Logic allows you to digitally record acoustic, electric and electronic instruments or vocal performances into your songs, and to process these audio recordings through Logic's built-in real-time effects. As with MIDI tracks, audio recordings are displayed in the Arrange window on an *Audio Track*.

These audio recordings are referred to as Audio *regions* in the Arrange window. Audio *regions* are actually visible portions of audio *files*. When you cut or resize an audio region in the Arrange window, the audio file itself is not cut or resized. The “region” that you see is a visual representation of a part of the audio file, and changes that you make to it in the Arrange window simply instruct Logic on *how* to play the audio file. In other words, the audio regions are simply “pointers” to the underlying audio file, and the reason they look like the MIDI sequences (with a waveform display when zoomed) is to make things easy to deal with. After all, you've spent the time learning how to deal with MIDI sequences, so it is reasonable to assume that the handling of audio regions should be similar. As it happens, they are!


Important!

It should be noted, however, that although the handling of audio regions and MIDI sequences is *similar* in Logic, it is not exactly the same. As a result, the editing and parameter options available for MIDI and audio tracks is slightly different.

Reload the Tutorial Song for more exercises.

Creating Audio Tracks

We will now create an audio track in the Arrange window, to which a drum loop will be added.

- Select the “Piano” track in the Track List, and create an audio track in the Arrange window via the **Functions > Track > Create** menu option, or by pressing . In the Arrange window, a new track will appear below the piano track.
- Click-hold on the “CHA 1” entry in the Track List, and a hierarchical menu will open.
- Browse to **Audio > Audio Track > Audio 1**, and release the mouse button. This will assign the track to the first Audio channel.




You can rename this audio track by clicking on **Audio 1** in the Track parameters box. It may make more sense to you if you were to name it “Drums”, for example. This name will be reflected in the Track Mixer, making it easier to identify when in this window. You can not rename the MIDI tracks associated with Multi-Instruments in the same fashion. Multi-Instrument MIDI track/channel names are defined in the Environment window.

It should be noted that an audio object must exist within the Environment (on the Audio layer) to allow its selection from the hierarchical flip menu in the Track List. If you require an audio track and no audio objects exist in a Logic song, you need to create them as per the instructions in the Environment chapter. Normally, when working with songs based on your Autoload song, this won’t occur, but on occasion, you may download or share song files with other users, and may find that no audio objects exist.


Important!

Track Mixer with Audio Channels

Audio and MIDI tracks can be controlled in a number of ways in Logic. The quickest method for level and pan control is via the Track Mixer, accessible via the **Windows > Open Track Mixer** menu or .



The Track Mixer horizontally reflects the track order as displayed—from top to bottom—in the Arrange window’s Track List. The viewing of different object classes can be changed in the Track Mixer window.

-  The updating of the Track Mixer channels is entirely automatic, so as you add or delete tracks from the Arrange window’s Track List, the Track Mixer will show or hide the corresponding MIDI or audio channel fader(s).

Once the Track Mixer is launched, you should see a new channel named “Audio 1” or “Drums” (dependent on how you named the track).

If you can’t see any audio objects, click on the **Global** button, to the top left of the Track Mixer.

The number of the corresponding track in the Arrange window is shown below each “fader”, or “channel strip”. Four further channel strips (Audio 2, Bus 1 and 2 and Master) appear to the right of the “Audio 1” or “Drums” channel. The two “Bus” channels are used as effects returns. The stereo “Master” fader acts as a master volume control for all audio channels.

- Change the audio channel from mono to stereo operation by clicking the button on the lower left corner of the channel strip. This is necessary, because we are going to import a stereo audio file.
- As a rule, you should use *stereo* tracks when importing (or recording) *stereo* audio files. Obviously, the same applies to *mono* files and *mono* tracks.
- Switch back to the Arrange window by closing the Track Mixer window.



The Audio layer of the Environment can also be used for audio mixing duties. It can be accessed from the Environment window, or by selecting the **Audio > Audio Mixer** menu option.

Tip

Changing the Track Mixer View

To the left of the Track Mixer window, you will see a collection of buttons, as shown. These buttons will toggle (hide/show) the display of particular classes of channel faders.

Global—Toggles the display between channels which correspond to those that exist in the Arrange window's Track List, and *all* MIDI Instrument and Audio objects which exist in the Environment.



When the *Global* button is inactive (gray) it will display the Arrange window's Track List channels. The other buttons can be clicked individually to display all channels of the selected class which exist in the Arrange window's Track List. Multiple classes can be selected for display in the Track Mixer by holding the **⌘** key while clicking on the individual buttons.

When the *Global* button is active (green) it will display all MIDI Instrument and Audio objects which exist in the Environment. The other buttons can be clicked individually to display all channels of the selected class which exist in the Environment. Multiple classes can be selected for display in the Track Mixer by holding **⌘** while clicking on the individual buttons.

Please try the various Track Mixer display modes with the Tutorial song to get a feel for how this view functionality works.

It should be noted that the display of additional classes of channel faders requires that the underlying objects actually exist in the Environment. If they do not, a *This song does not contain this type of object* error message will be displayed. You will need to create these objects as per the instructions in the Environment chapter.

Important!

Importing an Audio File

Now, let's import an existing audio recording of a drum loop into the Tutorial song.

- Select the **Pencil** tool, and click at measure 5 of the audio track. Logic will now ask for the files' location via the standard operating system file dialog.
- Browse to the drive and folder that contains the tutorial drum Loop—"Atmo-Drums.wav".
- Double-click on this file and it will appear in the Arrange window.
- As an alternative method, you can resize Logic. With both your desktop and Logic visible, you can browse to the Logic program folder and simply drag 'n drop the "Atmo-Drums.wav" file to the desired location in the Arrange window.

If you enlarge the display through use of the zoom bars or telescopes, you will see a waveform display in the audio sequence that was just imported. The audio file name is displayed above this waveform overview. A symbol indicating whether the file is mono or stereo will be shown at the end of the file name. Stereo files are indicated by two interlocked rings.




Start playback from measure 5, using one of the navigation techniques learned earlier. At this point, you should be hearing the audio file and will notice that the speed of the MIDI tracks and the drum loop are out of time with each other. We can fix this by adjusting the speed of the song.

Sample Editor

Open the Sample Editor by double-clicking on the drum loop region in the Arrange window. For precise editing of audio, this is the window to use. You'll notice that the starting point of the drum loop's waveform is not exactly aligned the first beat of measure 5.

- Enlarge the Sample editor display with the zoom bars or telescopes until you can see the waveform startpoint precisely.
- Move the start playback indicator—the small **S** icon below the waveform—so that it is perfectly aligned with the beginning of the waveform, as shown.




- Now press the button featuring the loudspeaker symbol, to listen to the audio file.

The startpoint should now be correct, but the audio region's end point must still be corrected. It must be moved forward (to the left) until the drum part loops smoothly. The best way to check this is by engaging “cycle” mode in the Sample editor. Do so by pressing the button shown.



- Scroll to the end of the drum loop and move the end point back (i.e. to the left). To do so, drag the end playback indicator—the small **E** icon below the waveform—until there are exactly two measures between the start and end points.



You should optimize the beginning and end points until the loop actually cycles smoothly. It should be noted that this can be done as the audio file is actually playing, which makes setting loop boundaries much easier. Listen to the loop and adjust these points until it cycles perfectly. This is very important, as the loop's length will be used to adapt the tempo of the song to the audio file.

Important!

- Once you're done, disengage the speaker button (by clicking on it again) and return to the Arrange window by closing the Sample Edit window.
- In the Transport Bar (or Bar Ruler), set the locator points to cycle between measures 5 1 1 1 and 7 1 1 1.
- Select **Options > Tempo > Adjust Tempo using object length & Locators**, or press **T**.
- At this point, you will be asked whether the tempo for the entire song (global) should be changed to match the audio file, or whether a tempo change should be inserted at the left cycle point, 5 1 1 1. If **global** is selected, your arrangement should look similar to this:
- Press **Play**. You'll notice that the song speed is adapted precisely to the drum loop, which you just defined using the locator points. The drum loop is two measures long. The length and position of the audio region (audio sequence) now corresponds exactly to the start and end point changes made in the Sample Editor.



You can move, cut, and copy the audio region in the Arrange window, just as with MIDI sequences. Please experiment with this, making use of the **Undo** function as you go.

As mentioned earlier, despite the similarities, the handling of MIDI and audio is slightly different. As such, the Matrix and Score editors, plus a number of MIDI-specific functions are not applicable to audio regions.

The Audio Window

Put simply, the Audio window allows you to manage all audio files used in the open song. Press **⌘G** to open this window or browse to it via the **Audio > Audio Window** menu option.

The Anchor

The changes you made to the “Atmo-Drums.wav” file in the Sample Editor have aligned the audio region in the Arrange window to position 5 1 1 1. While you can move the audio region directly in the Arrange window, by dragging it or using the **Delay** parameter in the region’s Parameter Box, you can also make use of the Audio window to adjust the *Anchor* point.

The *Anchor* point of each audio file has a direct impact on the audio region(s) which point to the file. To illustrate this, position your windows in a way that allows you to view the “Atmo-Drums.wav” region in the Arrange window and the “Atmo-Drums.wav” file in the Audio window.

- Select the “Atmo-Drums.wav” region in the Arrange window.
- Click-hold on the **up arrow** beneath the “Atmo-Drums” waveform overview in the Audio window, and drag it to the right.
- Release the mouse button around the center of the waveform graphic while keeping an eye on the audio region in the Arrange window. As you can see, the entire region was moved to the left.
- Select **Edit > Undo** to reverse the process.

In moving the *Anchor* point, you have adjusted the audio region's temporal (time) reference point. The *Anchor* can be used to quickly select the “downbeat”, for example, in a looped drum region in your arrangement.

The *Anchor* point can not be positioned before or after the *Sample Start* and *End* points, respectively.

Quick and Dirty Audio Regions

You can define region start and end points in either the Audio window, or directly in the Arrange window. Either method is useful for roughly defining a region's size. If you need precise control over the audio region/audio file start and end points (for loops etc.), please make use of the Sample Edit window.

Before commencing this exercise, please ensure that both the Audio and Arrange windows are visible.

- In the Audio window, select the tool which looks like a hand with an extended index finger.
- Click-hold on the left or right hand end of the “box” which encompasses the “Atmo-Drums” waveform overview, and drag horizontally. As you do so, the “box” will increase/decrease in size.
- Once the desired location has been reached, release the mouse button. While doing so, keep an eye on the audio region in the Arrange window.
- Now, in the Arrange window, select the Arrow tool, and grab either the left or right hand end of the audio region. As you do so, the cursor is shown as a hand with an extended index finger, and the region will increase/decrease in size.
- Once the desired location has been reached, release the mouse button. While doing so, keep an eye on the audio file overview in the Audio window.

If the Sample Edit window was also opened, you would see that the adjustments made in the Audio window adjust the *Sample Start* and *End* points. Adjustments made in the Arrange window, however, do not alter the *Sample Start* and *End* points.

Important!

The reason for this is that the Arrange window only deals with *audio regions*, not *audio files*. The Sample Edit and Audio windows, on the other hand, deal with the underlying *audio files* on which the *audio regions* are based.

Audio File Menu

This menu provides a range of file handling tools, including delete, backup, conversion and more. These tools can aid you in “housekeeping” tasks for all of the files used in the song. Please refer to the Logic Reference manual for detailed information on each function.

The Digital Factory

The Digital Factory is a collection of audio processing tools which can be used for a number of tasks, including pitch shifting and time stretching of audio material. You may follow this section now, or return to it at a later stage.

- Reopen the Sample Editor by double-clicking on the drum loop region in the Arrange window.
- Click on the **Factory** menu and take a look at the various options, one by one. The Reference manual contains detailed information and examples on the use of these tools, which you should consult while doing so.
- Please feel free to experiment with the various processes, making use of the **Undo** function as you work through them.

Making Your Own Audio Recordings

First, connect the sound source—a mixer, CD player, or microphone, for example—to the audio input(s) of your system. Create a new audio track, using the method described in the *Creating Audio Tracks* section, from page 156 onwards.


Arming Tracks

Unlike MIDI tracks, audio tracks must be “armed” before they can be recorded to, just as the tracks on a tape recorder must first be armed. There is a small button marked with an **R** to the left of each audio track in the Track List. Clicking on this icon prepares the audio track for recording. The **R** button will turn red, indicating that the track is armed. You can also click on the **REC** button on an audio channel in the Track Mixer, in order to arm the appropriate audio fader/track.



Setting a Record Path

Unless you’ve already configured your audio path, the following dialog will open. Key Command **[A]**.



Click on **Set** for your audio device(s), and in the dialogue window that appears, select the name of the audio file (by default, this is “Audio”) and path—i.e. hard disk location—for your recording(s).

Global and Song Record Paths

If a **Global Recording Path** is set, you do not need to repeat this procedure before every recording. Subsequent recordings will automatically be assigned the same name, with a number appended to the end of each file created. To do so, click-hold in the panel above the **Set** button. This will open a flip menu where you can select a **Global** or **Song Recording Path**. Please select the **Global Recording Path**, for now.

As you work with Logic, you will generate a great deal of audio data. To aid you in managing this data, we suggest that you make use of the **Song Recording Path** option, and follow the tip below.

It is recommended that you set up a different file name (and folder) for each new song you create, so that the song title and the audio files used in it are the same. As an example—The “rocksteady” song should be in the “rocksteady” folder. Your default audio file name should also be “rocksteady”, and be **Set** to record into this folder.

Tip

The advantage of working this way is that all songs and audio files associated with a particular project are contained in one place, and have an associated (or the same) name. This makes things much easier to find, if returning to a project after a period of time. It is also beneficial for archiving purposes.

The **Global Recording Path** is saved with the Preferences, and will be used as the “default” path the next time Logic is launched.

The **Song Recording Path** is saved with the Song file, and will be used as the “default” path the next time the specific Song file is loaded.

Using the Audio Object Name

This option in the **Audio Record Path** dialog allows you to make use of Logic’s ability to rename audio objects, as discussed in the *Creating Audio Tracks* section, from page 156 onwards. Such object names will then be used for audio files. As an example, if an audio object was named “Drums”, then all audio files recorded to that channel would automatically be named “Drums”, “Drums1” a.s.o. This facility becomes even more useful when used in conjunction with the **Song Recording Path** option.

Stereo Recording

To make a stereo recording, you must first configure the selected track's audio fader as stereo in the Track Mixer, or Audio layer in the Environment.



- Open the Track Mixer and click on the symbol to the left of the **REC** switch, on the *highlighted* audio fader. This will toggle the track between stereo and mono.



The symbol on the button indicates the current status as follows: A **single circle**—**mono**. A **pair of interlocked circles**—**stereo**. The level meter will also divide into two discrete meters, when an audio fader is set for stereo operation. While in the Track Mixer, note that there is now an additional “audio” fader. As you create new tracks—MIDI or Audio—in the Arrange window's Track List, a new corresponding fader will be created in the Track Mixer.

It should be noted that the underlying objects, on which the Track Mixer channels are based, must first exist in the Environment window. Also of note are the different view options available to the Track Mixer, as discussed in the *Changing the Track Mixer View* section, from page 158 onwards.

- Once you're done with setting the **stereo/mono** status of the audio channel, close the Track Mixer.

Levels

As soon as you arm an audio track, you will hear any signal being sent to the audio inputs of your system. The audio track's fader in the Track Mixer controls the level of the monitored signal—i.e. what you're hearing.

The fader always controls the *playback* level, *not* the recording level. Recording levels must be set externally—i.e. on your mixer, or at the original sound source.


Important!

Care must be taken when setting input levels, as digital audio will “clip” when overloaded. Clipping results in particularly harsh metallic distortion, so unless you have a penchant for heavier musical styles, we don’t recommend overloading the inputs.


It’s often quite useful to have the Windows mixer utility open while recording into Logic. This allows you to set an input level for your audio recordings which doesn’t overload Logic.

Tip

Starting to Record

- Start recording by pressing the **Record** button on the Transport Bar, or by pressing  on the numeric keypad. You will notice that a waveform is drawn, in realtime, in the Arrange window during recording.

Keep an eye on the level meter on the audio faders. In the event that the clip indicator (top, red LED) lights up, you will need to record again, using a lower level. To avoid having to watch the level meter constantly; the overload indicator remains lit until it is clicked. If your recording level was too high, ensure that you click on the overload indicator to reset it.

- Once you’ve finished recording, press **Stop** on the Transport Bar or by pressing  on the numeric keypad.

Congratulations, you’ve recorded your first audio file.

Please do not forget to disarm the track(s) after recording has finished. Do this by clicking on the illuminated (red) **R** button which will then turn gray. If the track is not disarmed, you will not be able to listen to the audio region on this track.

3.9 Mixer Functions

The Track Mixer (and the Audio layer in the Environment) can be fully automated. This automation allows a full “flying-fader” mixdown of all audio channels, master faders, busses, audio instruments and effects. This section covers the terminology and use of the various parts of the Track Mixer, and a brief look at the mix automation facilities available in this window.

Logic’s Arrange window features an enhanced track-based automation system, which is covered in the next chapter. We strongly recommend the use of this Track Automation system over the use of the older methods of previous versions.

Important!

Automatic Mixing


- Open the Track Mixer and the Arrange window. Resize both windows if necessary, so that you can see the Track List and a few of the faders in the Track Mixer.
- Select **View > Track Automation**. The Arrange window will zoom in vertically.
- Now click on any track in the Track List—MIDI or audio—and pay attention to the Track Mixer window. You will see that as you select a track in the Track List, the corresponding fader in the Track Mixer will be outlined in red.
- Select the **Touch** option by click-holding on the panel above the Pan knob on the outlined fader.
- To record changes to the volume, press **Play** on the Transport Bar (or use the Key Command) and move the “highlighted” fader up and down in the Track Mixer. As you do so, you’ll see a curved line being created on a gray “bar” in the Arrange window. Once done, press **Stop**.

- Return to the beginning of the newly recorded automation track, using any of the navigation methods you learned earlier, and press **Play**. Note that the fader on the Track Mixer is now replaying your recorded automation movements. This automatic playback of changes to the Track Mixer's channel parameters is often referred to as “flying fader” automation.
- The same automation method can be used for additional channels, pan knob position and also for the EQ parameters on audio faders. This also applies to plug-in automation, which we'll cover shortly.


Using the Equalizers

Equalization (EQ) is the process of boosting or cutting certain frequencies in an audio signal. EQ is used to make individual instruments or frequencies stand out (or the reverse) in an overall mix. Each audio channel in Logic features a number of parametric (or other) EQ's. All EQ parameters can be automated.

The desired EQ type can be selected from the **Thru** flip menu, found in the **EQ** section at the top of each audio channel strip. A stereo or mono EQ will be inserted automatically, dependent on the current status of the audio channel strip. The **ON** button is used to bypass or activate the EQ. The other parameter panels are described below:




- **Hz**: This control determines the center frequency of the band in Hz or kHz values.
- **dB**: This parameter determines the extent to which you can cut or boost a frequency band. At a value of **0.0** the EQ has no effect.
- **Q**: To minimize the EQ's effect on the rest of the sound, you can limit the bandwidth of frequencies around the center frequency value determined by the **Hz** parameter. The **Q** parameter determines this bandwidth. The greater the **Q** parameter value is, the narrower the filter band.
- Select the drum loop in the Arrange window.

- In the Transport Bar (or Bar Ruler), set the locator points to cycle between measures 5 1 1 1 and 7 1 1 1.
- **Solo** the drum loop.
- Launch the Track Mixer from the **Windows** menu or .
- Activate the EQ on the highlighted Audio channel by click holding on the **Thru** panel at the top of the fader.
- Experiment with different values in each of the parameter fields described above.
- Insert additional EQ's by click-holding on the other **Thru** panels, and try to isolate the kick (bass) drum, hi-hats and clap sounds, through careful use of the **Q** and **Hz** values. If possible, reduce/increase the gain (**dB**) to hear the individual parts of the loop in isolation.

Inserting Audio Effects

The internal audio effects of Logic can be inserted into the individual audio channels—regardless of type—by selecting the desired effect from a flip menu, accessible via the **Insert** “slot”(s) found on each audio channel strip. To insert an effect:

- Open the Track Mixer by pressing , or launch the Audio layer of the Environment by double clicking on the audio track you just recorded in the Arrange window's Track List.
- Once either “mixing surface” is open, click hold on any of the **Insert** slots on the audio channel, and a hierarchical flip menu will open, displaying the various effects, grouped in categories. Usually, you would insert effects from the top slot down.
- Highlight the category, and then the effect you wish to use in the flip menu, and release the mouse button. The **Insert** slot will turn blue, with the name of the selected effect displayed.
- To remove a plug-in from an **Insert** slot, click hold on the desired slot and select **No Effect** from the flip menu.

How Effects are Grouped

Logic “groups” effects as follows:

- Audio Channel Type—either Stereo, Mono/Stereo or Mono.
Stereo: Stereo in, stereo out (True stereo). Both input signals are processed separately, so the stereo qualities of the signal remain unchanged—this is important for summed or stereo bus signals used as inserts.
Mono/Stereo: Mono in/Stereo out. For use with mono signals only, but the effect output is stereo. Commonly used on the following mono signals: Chorus for bass, Reverb for lead vocal.
Mono: Mono in, mono out. Should only be used on mono signals. Typical applications are for EQ’s or dynamics processing (Kick, Snare, Bass).
- By API—**Logic, VST, DirectShow**. Grouping of effects in this fashion makes the selection of effects simpler.
- By effect definition—**Dynamic, Modulation, Reverb, Filter** etc. The effect definition groups effects of a particular type together. As an example, Chorus, Flanging and Phasing are different types of **Modulation** effect. This only applies to “native” effects.

Logic automatically limits the available effect types shown in the plug-in flip menus to match the audio objects signal I/O settings. In other words, if an audio object is mono, then *only* mono (and mono/stereo) effects will be available in the plug-in flip menu. This also applies to stereo audio objects with *only* stereo plug-ins being available. It is possible to override these settings by pressing and holding **Ctrl** before selecting the plug-in flip menu on an audio object.

Tip

If you choose to use a plug-in which does *not* match the audio objects’ signal I/O flow, Logic will be forced to do a data stream conversion, which places a greater strain on the CPU. This translates to fewer simultaneous effects, so keep this in mind.

Important!

The Plug-in Window

You can edit the effect's parameters by double-clicking on the (active) **Insert** slot, which will launch the plug-in window. Many of Logic's effects feature an enhanced graphical interface.


Please refer to the Reference Manual for specific information on the individual effects, their parameters and their use.

Effects Settings

Settings are used to store all parameter adjustments you make in the plug-in window. Every Logic and third-party plug-in allows the storage and recall of Settings. Effects Settings are accessible by click holding on the **Settings** flip menu (the downwards-pointing arrow) beside the **Bypass** button in the plug-in window.



- Within the **Settings** flip menu you can load an effects “preset” via the **Load Setting** option.
- To save your own personalized effects settings, adjust the parameters of the open plug-in window by click holding on any parameter, and moving the sliders/knobs. Once your parameter adjustments have been made, click hold on the **Settings** flip menu and select **Save Setting**. In the ensuing operating system file dialog window, type in an appropriate name for your Setting, and press the **Save** button. Please give this a try.
- You can also use the **Settings** flip menu to copy and paste parameters between Settings.

 Logic automatically creates a folder called “Plug-In Settings” when first installed. Within this folder, a separate folder for each effect is created. When you use the save/load preset functions in the Settings flip menu, Logic will automatically save/load the Setting file to/from the corresponding effect folder. As each effect Setting is stored in its own associated folder, you should find it easy to manage hundreds of presets. This feature is applicable to all Logic and third-party effects.

It is recommended that you do not attempt to change the folder structure within the “Plug-In Settings” folder.



Important!

Reassigning Plug-in Windows

Rather than opening a separate plug-in window for every effect on every channel—which would involve a lot of effort and require massive amounts of screen space—you can reassign any open plug-in window in two different ways, using the two flip menus in the gray area of the plug-in window:




- Using the **upper flip menu** (typically showing a channel name) you can switch the editor window between all channels using this specific plug-in. E.g. if you have applied a Compressor to tracks 1/2 and 3/4, you can switch between these channels and adjust the parameters independently for each instance of the Compressor.
- In the **lower flip menu** you can switch between the plug-ins selected for that specific channel. E.g. if one channel uses a Chorus and a Delay plug-in, you can switch the window between the two effects.



Changing the Plug-in Display

Many—although not all—of the effects feature an **Editor** button which allows you to toggle between the graphical “Editor” and the **Controls** view of the plug-in. The Controls view displays *all* of the plug-in parameters, and often saves space onscreen.



The Editor and Controls views of the Tape Delay plug-in. Note all of the parameters preceded by an asterisk (*) at the bottom of the Controls view. These parameters are not visible in the Editor view.

Additional Plug-in Window Options


The gray area of the plug-in window displays a **Link** button and a **Bypass** button, and *may* contain an **Extra Controls** button, shown in the centre of the image. To explain their use:

- Insert a plug-in in the first **Insert** slot of the first Audio channel, if you have not already done so.
 - Double click on the illuminated **Insert** slot and the floating plug-in window will launch.
 - Now insert a different plug-in into the second **Insert** slot of the audio channel. You will notice that the open plug-in window updates to show you the newly selected plug-in.
 - Click on the **Link** button to the left of the gray plug-in window area.
 - Now insert a different plug-in into the third **Insert** slot of the audio channel. You will notice that the a new plug-in window is automatically spawned for the newly selected plug-in.
- These two plug-in window behaviors may be useful for different tasks, when assigning effects and mixing in Logic.

The **Extra Controls** button—if available to the plug-in—is activated by simply clicking on it.

- Click hold on the first **Insert** slot, and select the **Logic > Delay > Tape Delay** plug-in, and launch the plug-in window if one is not already opened.
- Click on the **Extra Controls** button, just to the right of the **Link** button, and the plug-in window will expand to display the additional parameters available to the *Tape Delay* plug-in. This gives you the best of both worlds, allowing you to make use of the graphical interface of the plug-in, while having access to all options.

The **Bypass** button is used to “bypass” the effect. This is useful for allowing comparisons of an audio signal with and without the effect. Bypassing an effect is achieved by simply clicking on the **Bypass** button when in the plug-in window.

If you wish to bypass an effect when no plug-in window is opened, press  and click on the desired channel’s **Insert** slot. The bypassing of any plug-in can be automated, so remember this option if the effect is not in use during a particularly “busy” part of your song, and you need more processing power—i.e. if there’s a lot of other effects and/or softsynths in use.

Tip

Using the Effect Buses

Effects on Audio Track, Audio Instrument and Audio Input channels can be routed to Audio Return (Bus) channels. These Audio Bus channels can, in turn be routed to other Bus channels or Master Outputs. To “send” an Audio Track, Instrument or Input to a Bus:

- Click hold on any of the **Bus Send** slots, and a hierarchical flip menu will open, displaying the available Buses.
- Highlight the desired Bus number, and then release the mouse button. The **Bus Send** slot will turn blue, with the name of the selected Bus displayed. A small knob will appear to the right of the **Bus Send** slot. This is the **Send Level** control. It determines the amount of signal which is sent from the Audio channel to the Bus channel.

- To adjust the amount of send level, click hold on the knob and drag your mouse to the right. You may also press **90** and click on the knob which will automatically set it to a value of **90**.
- Insertion of an effect on a *Bus channel* is as per effect insertion on the other audio channel types.

Serial and Parallel Effects Setup

To offer a brief description:

- In a *Serial Configuration*, the output from one effect is summed with its incoming signal and fed into the input of the next effect in a chain. A series configuration will occur in Logic when you insert multiple effects into subsequent **Insert** slots on a single audio or Bus channel.
- In a *Parallel Configuration*, the Bus Sends from each channel are fed to multiple Bus channels (with inserted effects) simultaneously.
- The results from these two methods of adding effects to an audio source is dramatically different, even if the same effects are used, in the same order.

You can set up effects—in series—on a single bus, which work exactly like the Inserts on a single channel. This way, you can route multiple audio channels through one bus, with a particular serial effects combination, saving you time in setting them up, and also conserving CPU resources.

Tip

This type of flexibility allows you to combine different effects in different ways, so that you can build your own complex multi-effects, which are saved as part of your song files. You may wish to set up such a configuration and save it in your Auto-load song.

What Sort of Effects Go Where?

Although there are no “unbreakable rules” about what effects types should be used, there are a number of traditional uses which make sense. The amount of processing power required for particular types of effects—particularly reverbs and Logic Platinum’s Spectral Gate—demand that they be used judiciously.

Traditionally, reverb effects are inserted into Buses, allowing multiple tracks to make use of a single reverb “unit”. As the **Send Level** knob(s) on each audio channel can be used to control the amount of signal sent to the Bus(es), the amount of reverb applied to each channel’s signal can be varied. This traditional use makes sense in Logic too, given the CPU resources required by the reverb effect.

Dynamics processing and equalization is generally applied on a per-channel basis. The CPU requirements for these types of effects are far lower than that of a reverb.

Other effect types, such as modulation processes—chorus, flanging etc.—can be used in either the Bus or channel **Insert** slots, but are generally used on Buses. Delays are commonly used on Buses. Filter effects are usually channel-based.

Logic’s distortion effects do not incorporate a level control, and are best suited to use on Bus channels.

Feel free to make your own choices, based on what provides the “right” sound for your music, but please take the processing requirements and channel status—mono, mono/stereo/ stereo—of the signal path into account.

About Summed Levels

In digital recording systems such as Logic, each “process”—volume, panning, adding an effect etc.—performs a data calculation. These calculations often result in an increase or decrease of the perceived level of the signal—i.e. signals can become louder or softer with each process.


As digital audio is unforgiving when signals are too “loud”, you must ensure that you keep an eye on your level meters when feeding your audio channels to Buses and Master outputs directly, or via effects.

At each step of the signal path, signals are “summed” together, so take care in setting each of the effect, channel fader, bus send, bus fader and master fader levels. This way you can avoid clipping and digital distortion, ensuring that you get the cleanest possible sound.

Audio Instruments


The next thing we’ll look at is the use of the Audio Instruments. Audio Instrument channels are designed for use with software based synthesizers, samplers, drum machines and the **EVOC 20** vocoder.

To create an Audio Instrument track:

- Select the “Piano” track in the Track List, and create an audio track in the Arrange window via the **Functions > Track > Create** menu option, or by pressing . In the Arrange window, a new track will appear below the piano track.
- Click-hold on the “CHA 1” entry in the Track List, and a hierarchical menu will open.
- Browse to **Audio > Audio Track > Audio 1**, and release the mouse button. This will assign the track to the first Audio channel.
- Double click on the Audio 1 Track, which will launch the Environment window’s Audio layer.
- Click once on the background of the Environment window, which will deselect the Audio 1 object.
- Create an Audio Object by selecting **New > Audio Object**. This will generate a small “waveform” icon onscreen.
- Double-click on the icon to change it’s appearance to an audio fader.



- Clicking on the **Cha** entry in the Audio object's parameters box will allow you to select an Audio Instrument object via a hierarchical menu, as shown in the following diagram.




- Once you have selected **Audio Instrument 1**, release the mouse button.

Click hold on Audio Instrument 1's top **Insert** slot, and select the **mono > es-m** synth. Also available from Emagic are the **ES1**, **ES2**, **EXS24** and **EUP88** software instruments, which can be purchased separately.

It should be noted that if an Audio Instrument object already exists within the Environment (on the Audio layer) it can simply be selected from the hierarchical flip menu in the Track List.


Tip

- Once you've made your selection, a double-click on the slot will launch your synthesizer's plug-in window, and as you'll discover, there are lots of knobs, sliders and more to experiment with. This we'll let you try on your own. By default, the plug-in window will automatically launch.
- To actually record some new music using your selected Audio Instrument, you need to return to the Arrange window, so for now, close the Track Mixer window.

- Recording Audio Instruments is just like recording MIDI instruments, so simply press **Record** on the Transport Bar (or use the Key Command—) and start playing your MIDI keyboard.
- Once you're done, press **Stop**.
- Audio Instrument tracks can be edited in the same fashion as MIDI tracks, although there are some small differences, as discussed in the next section.

Remarks on the Use of Audio Instruments

Audio Instruments generally use more CPU resources than traditional effects, so you need to be judicious about their use, particularly if your computer isn't a cutting-edge machine. Follow these tips to reduce system load if you find your system struggling and your audio or Audio Instruments start to 'glitch' on playback.

Please note that muting an Audio Instrument track in the Arrange does *not* reduce system load. You can, however, bypass the instrument by pressing  and clicking on the Audio Instrument channel's **Insert** slot. The bypassing of an Audio Instrument can be automated, so remember this option if the synth is not in use during a particularly "busy" part of your song—i.e. if there's a lot of other effects and/or softsynth use.

When an Audio Instrument track is selected, it is ready to be played in realtime and consequently produces an amount of system load. Normally, Logic releases system resources used by the Audio Engine when the sequencer is stopped. This is not the case, however, if an Audio Instrument track is selected in the Arrange window, and is available for real-time playing. Selecting a MIDI track or a standard audio track exits this "stand by" mode and releases reserved system resources, when the sequencer is stopped.

Audio Instrument tracks can be processed by the **Quantize**, **Transpose** or **Delay** sequence parameters in realtime.

To hear Audio Instrument plug-ins in conjunction with plug-in effects, Logic must be in play mode. As with all of the other plug-ins in Logic, you can alter the parameters of the Audio Instruments and save your own *Settings* for later recall. Please read the *The Plug-in Window* section, from page 173 onwards.

You may notice a delay between playing your keyboard and hearing the sound. This is another form of latency, as we discussed in Chapter 1. Please refer to this chapter and the separate Installation Guide for tips on adjusting your audio card settings to minimize this latency. It should be noted that you may not be able to completely eliminate this “gap”, as this form of latency is completely reliant on your sound card’s driver.

Important!


A Quick Word on the Included Instruments

The three synthesizers provided with Logic are briefly described below. Coverage of all parameters can be found in the online help system and Reference manual.

- The **es-m** is a monophonic “bass” and lead sound synth, modelled on the venerable Roland TB-303 Bassline, but offering a number of enhancements on the original.
- The 8-note polyphonic **es-e** is great for warm and lush “pad” sounds.
- The **es-p** is also polyphonic, and is well suited to the creation of finely-crafted percussive sounds with fast attack phases, pads, brass and more. It offers a number of creative facilities over the other two synthesizers, making it the most versatile of the three.


Plug-in Automation

Parameter adjustments of all effect plug-ins, including software-based Audio Instruments, can be recorded and played back in realtime, just like the level faders and pan pots on audio channels.

 It should be noted that some effect types supported by Logic are not designed for realtime use—e.g. Premiere, AudioSuite. These plug-ins

are used “offline” in the Sample Editor. Please consult the Logic Reference manual for further information on their use, if applicable to your system.

The procedure for effect parameter automation is as follows:

- Open the Track Mixer by pressing .
- Select **Touch** or **Latch** mode from the panel above the pan knob on the audio channels with the plug-ins you want to automate.
- Double click on an **Insert** slot which contains an effect. (Insert one, if none are active.)
- Press **Play** and move the sliders and knobs in the plug-in window. An automation track will be recorded, but will not appear in the Arrange window.
- Press **Stop** when done.

The newly created automation data can be seen by selecting **View > Track Automation.**, and by then selecting the appropriate “slot” and parameter in the top panel of the track. More on the automation system is found in the next chapter.

Tip

3.10 More Files to Try Out

The “Tutorial Song Audio/1” file is an example of a combined MIDI /audio arrangement, based on the original Tutorial song. The delay and quantizing parameters of the MIDI tracks were changed, as the swing groove value originally chosen does not work well with the drum loop. Effects from the Track Mixer were added to the drum loop and rap sequence. Load it up.

There is a stereo file named “Audio Tutorial (2 Track)” on the Logic CD. This is the outcome of edits to the audio portion of the tutorial. This is a mini audio master of the “Tutorial Song Audio/1” file.

Now It's Your Turn ...

If you've worked through the Tutorial up to this point, then you should have a good overview of Logic's most important functions, and a working knowledge of its operation.

The Reference manual and on-line help system provide detailed information on the different parts of Logic. Please make use of this documentation if you need specific assistance on any function or parameter. Given what you have learned throughout the Tutorial and preceding chapters, you will benefit greatly by reading the Reference manual.

Before leaving the Tutorial chapter, we'd like to thank you for sticking with it. Please run through it again, if you'd like more practice, or try out some of the suggestions below.

The Tutorial song contains useful source material for your own experiments. We encourage you to spend some more time working with it and that you give the following a try.

- Record more tracks—MIDI and audio (e.g. percussion, vocals), or Audio Instruments.
- Test out the different Audio Instruments, and create some of your own preset *Settings*.
- Replace existing tracks with your own recordings, e.g. piano, bass, drum parts.
- Create more audio tracks, and insert additional audio files.
- In the Sample Editor, experiment with the various **Functions** and **Factory** menu options, and listen to the results on a range of different audio files.
- In the Track Mixer window, use the Bus and channel **Inserts** to add effects to the audio tracks. Experiment with different delay, reverb (and other effects') parameters by entering their plug-in window editors.
- Look for mistakes in the sequences, and remove them by using the various editors.

That concludes our Tutorial, and this portion of the manual.

Have Fun.

Chapter 4

Mix Automation

This chapter will introduce you to Logic's track-based mix automation functions. In preceding chapters, we looked at the *HyperDraw* function and the *Track Mixer* window for adjusting and automating mix and other parameters. These include volume and panorama changes, plus real-time changes made to effect parameters.

In addition, we've also explored the mute and solo, effect bypassing and other functions, plus the use of *continuous controllers* which provide you with control over your MIDI devices.

Logic Version 5 (and up) expands on these facilities with an enhanced, elegant *Track Automation* system which is accessed directly in the Arrange window. Being able to perform virtually all recording, editing, arranging and mixing tasks in a single window is both convenient and efficient. This automation system can be used either "offline" or "live", which we'll discuss in this chapter.

The Track Automation system supports 32 Bit fader values which, in practical terms, means that it's very precise. This affords extremely detailed realtime, automated control over your Audio, Audio Instrument, effect and MIDI parameter settings.

Logic Version 5 natively supports the Logic Control and Logic Control XT units. These hardware devices are connected to your MIDI interface and provide control over many Logic functions, including mixing, transport and more. Many of the procedures outlined in this chapter can be achieved more quickly and easily with the Logic Control. For further information, please visit www.emagic.de or contact your local Emagic distributor.


4.1 About the Mix Demo Song

As you work through this chapter, use the provided “Mix Demo” and “Mix Demo Edit” songs. Both songs feature a number of tracks configured for General MIDI (GM) tone generators. Please refer to the Tutorial chapter for information on adapting the song to your tone generator, if you do not have access to a GM unit.

The “Mix Demo” song also makes use of Logic’s built-in software synthesizers, the **es-m**, **es-e** and **es-p**.




Load the Mix Demo Song

You can start the “Mix Demo” Song by starting Logic, selecting **File > Open**, and browsing to the song, or by double-clicking on the “Mix Demo” song icon in the Logic folder.





The Mix Demo song.

Play the Mix Demo Song

- To listen to the Mix Demo Song, simply press  on the numeric keyboard.
- To stop the song, press the  key.
- To return to the beginning of the song, push , on the numeric keypad, twice in succession.



Song Screensets

A number of Screensets have been defined in the Mix Demo Song. Press the numeric keys  through to  to familiarize yourself with them.

4.2 Track Automation Basics

As the name suggests, Track Automation is tied to a specific *track* in the Track List of the Arrange window. When Track Automation is enabled, and an *automation event type* is defined on a given track, a transparent gray bar (automation track) will appear, aligned with that track. This transparent gray track runs the entire length of the song.



The images above show two sequence objects. The lower image is shown with Track Automation enabled. Note that the gray automation track runs across both sequence objects. Also note the percentage value 28.346. This is a 32 Bit fader value, ensuring incredibly accurate and fine control over parameters—filter Cutoff frequency, in this case.

Viewing Track Automation

Track Automation can be shown/hidden by selecting the **View** > **Track Automation** menu option.



- Please select Screenset 2, and toggle the Track Automation view. As you do so, you'll notice that the individual tracks will automatically resize vertically to accommodate the additional parameters shown on each track in the Track List. Relative size differences between zoomed and unzoomed tracks is retained.
- Switch to Screenset 1. As you can see, the hide/show status of Track Automation data is specific to each individual screenset which contains an open Arrange window.
- Switch back to Screenset 2.

Important Information

Logic's Track Automation is discrete from the **Record** function for Audio, Audio Instrument and MIDI tracks. In other words, Logic does not need to be in *Record* mode in order to write new automation data to tracks. In addition, the track you wish to automate does not need to be selected in order for automation data to be written to it.

Track Automation data can be written “offline” or “online”.

- *Offline*—means that Logic is not in *Play* or *Record* mode. When offline, you can use your mouse to insert “nodes” just as with the HyperDraw function. In fact, the Track Automation facility is an advanced version of the HyperDraw function.
- *Online*—means that Track Automation data is written “live” as Logic is running. This can be achieved using on-screen faders, knobs and switches in the Track Mixer and plug-in window, or with an external controller, such as the Logic Control.

Track Automation data can be “tied” to specific sequence objects or audio regions, allowing you to move a sequence/ audio region and have the automation data move with it. Track automation data can also be completely independent of MIDI sequence objects and audio regions. The choice is yours.

Important!

HyperDraw & Track Automation Compared

To illustrate the differences between the Track Automation and HyperDraw facilities, we ask that you read and try the following.

Both the HyperDraw and Track Automation functions allow you to visually insert (or record) a set of “nodes”—i.e. “dots” on the Automation track or HyperDraw “window”. These “nodes” are automatically connected by both functions as a segmented line, as shown below.



HyperDraw is shown on the left, and the same data is shown in it's Track Automation form on the right.

Numerical values for the current automation track are automatically displayed at nodes, if there is sufficient space between the nodes.

Numerical values are context sensitive (e.g. center of pan is displayed as **0** and not **64**, volume values are displayed in **dB**—decibels).

Important!

You can view both HyperDraw and Track Automation data simultaneously in the Arrange window *on different tracks*. If a MIDI sequence object or audio region which contains HyperDraw information is placed on a track with Track Automation enabled, the HyperDraw information will be “hidden”. The HyperDraw information will still exist, but won’t be visible.

Important!

To use HyperDraw (and do give it a try):

- Select the *Piano Chords* sequence at Bar 1.


- Open the **View > HyperDraw** menu and select **Volume** in the list, then release the mouse button.
- This will turn the *Piano Chords* sequence blue, provided it is “zoomed” in enough. Use the zoom controls to get a “close up” look, if the blue background is not visible.
- To insert “nodes”, click directly in the blue area of the sequence at any point(s) along it’s length with the **Pencil** or **Arrow** tool. This will insert Volume change messages at these “nodes” and a line will automatically “connect the dots”.

You will note that the HyperDraw data is contained within the boundaries of the *Piano Chords* sequence. Please move the sequence to bar 5, and release the mouse button. Note that the HyperDraw data is moved with it. Return it to bar 1, once done.

- Now, select the *Piano Chords* sequence, and browse to the **Options > Track Automation** menu.
- Select the **Move Current Object Data To Track Automation** function, and release the mouse button. As you can see, the HyperDraw data you inserted has been “converted” to Track Automation data. This automation data track continues beyond the boundaries of the *Piano Chords* sequence. Also note that new information has appeared in the Track List panel beside the sequence.



As with the HyperDraw data, Track Automation data can also be moved with the sequence (or audio region). Please give it a try by dragging the *Piano Chords* sequence to the right. When you release the mouse button to “drop” the sequence, you will see the following dialog box.




Select **No** and pay attention to what happens to both the sequence and the Automation Track data. We will get to the other options in this dialog box shortly.

4.3 Track Automation Menu

The Track Automation functions are found in the **Options > Track Automation** menu.

Automation Settings...

Selecting this menu option will launch the following window.



The **Move Automation with Objects** parameter is a flip menu with the choices **Ask**, **Always** and **Never**. This is where you can set your preference for the behavior of the Track Automation system when you move objects. It is tied to the dialog box you saw a moment ago, when you moved the *Piano Chords* sequence.

Ramp Time is important for the “Touch” mode of faders. It determines the time (in milliseconds) that it will take a fader to smoothly return to its previous value, once you have released the fader. We’ll get to fader “modes” in the *Track Automation Modes* section, from page 193 onwards.

“Write” Mode erases: determines the type of automation data that is erased when “Write” mode is active.

“Write” Mode changes to: determines the “mode” that the automation system automatically changes to when the “Write” mode has completed erasing the automation data.

Delete Functions

The Track Automation menu contains three delete functions. To illustrate these, please:

- Select track 5 of the Track List (The *Piano Chords* track).
- Click hold on the **Cha 1 Volume** panel of track 5 in the Track List.
- In the ensuing flip menu, select **Pan** and release the mouse button. While you have the flip menu open, browse through the two **MIDI Control** menus. Once you've released the mouse button, the panel will update to display the automation data type—i.e. “pan”.
- Insert a few “nodes” along the length of the *Piano Chords* automation track.
- Now, select the **Options > Track Automation > Delete currently visible Automation Data of Current Track** option. The “pan” automation data for track 5 has been deleted, and will disappear from the Arrange window.
- Click hold on the **Cha 1 Pan** panel of track 5 in the Track List, and in the ensuing flip menu, select **Volume** and release the mouse button. You'll see that your *Volume* automation data was untouched by the deletion.
- Click hold on the **Cha 1 Volume** panel of track 5 in the Track List, and in the ensuing flip menu, select **Pan** and release the mouse button.
- Now, select the **Edit > Undo HyperDraw** menu option and confirm the “undo” in the ensuing dialog box, which will return your *Pan* automation track to its former glory.
- Browse to the **Options > Track Automation > Delete All Automation Data of Current Track** option. All of your *Volume* and *Pan* automation track data will be erased.
- Once again, select the **Edit > Undo HyperDraw** menu option and confirm the “undo” in the ensuing dialog box. This will restore your *Volume* and *Pan* automation track data.
- The final delete function is pretty self-explanatory. It deletes all data on all tracks, whether they are selected or not. Don't try it out, at this stage.

Move Functions

We introduced you to the **Options > Track Automation > Move Current Object Data To Track Automation** function when we “converted” the HyperDraw *Volume* information into Track Automation *Volume* data.

Where it differs from the **Options > Track Automation > Move All Object Control Data To Track Automation** function is as follows:

- The “current” object data of the top “move” function refers to the automation data type that is visible in the Arrange window, and the Track List panel.
- “All control data” is therefore pretty logical. In our deletion example, we created a *Volume* and *Pan* automation track. If we had used the “move all” function, both the Pan and Volume information would have been moved.

4.4 Track Automation Modes

Please select Screenset 1, and take a look at the faders in the Track Mixer. You will notice a black panel with the word **off** visible in it, just above the Pan control and the level meter. This is a flip menu which enables the different fader modes. Click-hold on the panel to view the options. Track Automation modes are available individually for all Audio Tracks, MIDI Tracks and Audio Instrument Tracks.




- **Off**—Automation is off. The fader will neither send nor receive automation data. Existing automation data remains untouched. It will still behave as a fader, however, and will adjust the volume or pan position etc. as usual.
- **Read**—The fader will read (follow) any existing automation data, but will not write data, regardless of any movements you make with the mouse or external control device.

- **Touch**—Writes new fader moves when the fader is “touched” during playback. This is obviously more relevant to a hardware device like the Logic Control, but also applies to the mouse. Any existing track automation data (of the current fader type) will be replaced by new movements as long as the fader is active—i.e. mouse button is depressed or a Logic Control fader is being touched.
- **Latch**—Similar to Touch mode, but the control remains activated, even when the fader/mouse is no longer being “touched”. In other words, following the release of the fader, the current fader value will replace the existing automation data as long as the sequencer is in playback mode. Press **Stop** to finish.
- **Write**—Overwrites ALL existing automation data of the data types selected in the automation settings, or creates new automation data. Only use it if you wish to destroy all existing automation data of the selected types.
- **MIDI**—Disconnects the fader from the Track Automation. The fader will act like a standard external MIDI control source and will be recorded and played back as normal MIDI data in MIDI sequences.

When Logic is not playing—i.e. it is in *Stop* mode—the Automation write modes are ignored and *no data is written* if the fader is moved. If there are no dynamic changes (i.e.—no movements of the fader), the current fader setting becomes valid for the whole song. This is always the case when you start a fresh song.

Important!



- Please select Screenset 2. In the Track List of the Arrange window which is displayed, you will notice that the *Audio 1*, *AudioInst 2* and *Warm Pad* tracks—tracks 1, 2 and 6—have been resized.

- On the *Audio 1* track, you'll notice a yellow "fader" to the right. This is ideal for "set and forget" setting of Automation data values/levels, saving you the trip to the Track Mixer window. This Track List fader automatically updates to "follow" changes to the currently visible automation track data. It can also be used for writing automation data, but you may find the Track Mixer's faders more convenient to use.
- The *Warm Pad* track also features a similar fader to the right. In this case, it is assigned to *Pan*.
- Click hold and drag on both to see how they visually change. Also note the automation track "line" while doing so.
- To the bottom left of the *Audio 1* and *Warm Pad* tracks, you'll notice a small panel with the word **Off** written in it. Click hold on this panel on the *Audio 1* track.
- As you can see, this flip menu is identical to that in the Track Mixer, allowing you to select the desired Automation mode directly in the Arrange window.
- On the *AudioInst 2* track, you'll notice that the Automation mode panel is missing. Click briefly to the right of the *AudioInst 2* track name, to select the track.
- Now, move the cursor towards the bottom left hand corner of the *AudioInst 2* track and keep an eye on it. When it changes into a hand with an extended index finger, click hold on the mouse button and drag down. This will resize the track.
- Release the mouse button when the desired vertical track zoom size is reached/when you can see the Automation mode panel.

4.5 On/Offline Automation

We have mentioned “live” and “offline” automation throughout the chapter. To explain further:

Online or “Live” Automation

Online/Live creation and editing of Track Automation data is achieved by the use of a “controller” while Logic *is* in Play or Record mode.

A “controller”, in this sense, could be a physical fader or knob on a hardware device such as the Logic Control. A “controller” could also be a software fader, slider or knob found in Logic’s Track Mixer (or Environment).

Important!

This “live” method of writing and editing Track Automation data is much more intuitive, not to mention faster. In essence, you “perform”—quite literally—your mixes in real-time as you’re listening to your music.

Writing “Online” Automation Data

- Please switch to Screenset 1.
- Select the Arrange window title bar to bring it to the foreground and select the **View > Track Automation** menu option.
- Click hold on the **Read** mode label of the *Audio 1* fader in the Track Mixer window.
- Change it to **Touch** mode.
- Start playback of the song.
- Grab the volume fader of the *Audio 1* channel in the Track Mixer window, and adjust it as you’re listening to the playback. Keep an eye on the *Audio 1* track in the Arrange window.
- Stop playback when you’re done.
- Return to the beginning of the song and press **Play** and watch your Track Mixer faders.
- If you don’t like your mix automation, simply start playback again and overwrite your existing data with new data.

Note that if you do overwrite your existing data, the fader will still be in **Touch** mode, so you will need to continue “touching” it while overwriting the data.

Tip

Try out the other modes on this, and the other tracks.

Offline Automation

Offline creation and editing of Track Automation data is achieved by the use of the mouse, when Logic *is not* in *Play* or *Record* mode. In fact, when you clicked in the *Volume* and *Pan* “nodes” on the *Piano Chords* track, you were creating “offline” automation data. As such, you already know the technique, so we won’t repeat ourselves here.

The offline use of the Track Automation facilities is best suited to editing tasks on existing automation data. This said, however, it can certainly be used as the primary input method. It’s your choice.

4.6 Automating Plug-in Parameters

You will notice that the *AudioInst 2* track also displays an Automation track assigned to **Cutoff**. This refers to the *Resonance Cutoff* control of the **es-p** synth assigned to this Audio Instrument channel.

Online Automation of effect and Audio Instrument parameters can only be performed in the plug-in window. You can perform “offline” automation of effect and Audio Instrument plug-in parameters directly in the Arrange window.

Important!

Any effect or channel parameter can be automated online, regardless of the *automation type* selected in the Track List. The display automatically switches to the parameter being written.


Important!

- Please double click on the **es-p** panel in the AudioInst 2 channel of the Track Mixer. This will launch the plug-in window.
- Set the appropriate “mode” (Touch or Latch) in the Track Mixer.
- Start playback and adjust the **Cutoff** knob in the **es-p** plug-in window by click holding and dragging (vertically) on it.
- Once you have completed your *Cutoff* automation, press **Stop**.

This technique can be applied to *any* effect parameter in *any* “Slot”.

Effects “Slots”


You will often use multiple effects on individual channels, busses etc. Each effect **Insert** slot is recognized, and enumerated by the Track Automation system. **Slot 1** is the top **Insert** “panel” on the channel fader, **Slot 2** is the second **Insert** “panel” a.s.o.

 *Slots* are helpful aids for identifying and separating the parameters of each effect inserted on the channel. As an example of where this delineation may be useful, many effect plug-ins feature a number of identically named controls. (i.e. “Mix”, “Low Cut”, “High Cut” etc.) In this scenario, it could become difficult to identify which plug-in the “Mix” parameter you were writing/adjusting belonged to. A quick glance at the Slot value will ensure that the appropriate “Mix” parameter is being adjusted.


Tip

Click hold on the **1 Cutoff** panel on the *AudioInst 2* track in the Arrange window Track List. You will see a hierarchical menu like that shown in the image. To explain:

- **Main**—are the primary channel “controllers”. They include Volume, Pan, Balance, Solo, Mute and Bypass functions.
- **es-pp**—menu entry contains the specific parameters for the **es-p** synth plug-in. All parameters that can automated in the plug-in are shown.



- **Tape Delay**—menu entry contains the specific parameters for this effect plug-in. All parameters that can be automated in the plug-in are shown.

 The entries shown in the menu (below the Main entry) reflect the plug-in “slot” order, as they appear in the associated channel fader. In this example, for *AudioInst 2*, the **es-p** would be “Slot 1”, and the Tape Delay would be “Slot 2”.

4.7 Editing

Please load the “Mix Demo Edit” song file for further exercises.

This section will introduce you to the techniques needed to make corrections and edits to existing automation data. You will also get a “feel” for handling of the automation data and should find it quite an “organic” and intuitive process.

On launch of the “Mix Demo Edit” song, you’ll see an Arrange window with a zoomed *AudioInst 2* track, which contains an amount of Track Automation data. The automation data consists of several “nodes” connected by lines. Above or below each node, you will see a numerical value which indicates the “level” (as a percentage in this case) of the node.

Nodes and connecting lines can be interacted with directly through use of the mouse. You can select nodes, lines, or a combination of both while editing. You can also make use of “modifier” keys to change the behavior of the mouse when you click on lines or nodes.

Handling Nodes

Inserting Nodes

A short click anywhere in the automation track will insert a node at that position and value. A short click on, or just outside a line, will insert a node on the line. Please try this.

Deleting Nodes

To delete a node, simply click on it *quickly* i.e.—a short click. The position of the node will determine what happens to the automation data. Try these and use the **Undo** or **Revert to Saved** functions between each.

- Click on the first node, and it will be deleted. This will, in turn, make the second node the first node. A click on this node will delete it and make the (original) third node, the first node a.s.o.
- The same also applies to the last node, but works backwards from the last, second to last, third to last nodes a.s.o.
- Clicking on a node which falls between two other nodes will delete it, and the nodes which surrounded it will be joined directly by a recalculated line. To illustrate this, click on the forth node (bar 7—value of 57.480).

Moving Nodes


The behavior of nodes, when moved, is best illustrated by actually doing it. Please follow these steps.

- Click and hold on the third node (around bar 5—value of 37.795).
- Now, slowly drag it to the left.
- Continue dragging until it passes the position of the second node and watch what happens. Ensure that you keep the mouse button depressed.
- Now, move back to the right and watch what happens. When you've neared the node's original position, release the mouse button. You can freely move to the left or right, and the behavior will be the same.
- Click hold on the node again, and drag it vertically, again passing the vertical positions (values) of the nodes above it. Return it to it's former position when done.



Moving Multiple Nodes


It is possible to select and move multiple nodes (and therefore the lines which connect them). You can move adjacent nodes—i.e. nodes that are beside each other—or you can move non contiguous nodes. Please follow these steps.

To select adjacent nodes:

- Click and hold on the line between nodes 2 and 3. Alternately, you can hold  and rubber-band select the desired automation area.
- In the dark gray area which appears, drag horizontally and vertically to see what happens.

For non-adjacent nodes, the technique is slightly different:

- Press and hold  and click on the nodes (or lines) you wish to select directly. Do this with node 2, node 7 (bar 13—value 57.480) and the last node.
- If you click the wrong nodes, simply click them a second time.
- You will notice that the nodes visually change from a solid to a hollow dot, indicating that multiple nodes are selected.
- Once again, release , click hold on any of the gray areas and drag horizontally or vertically.

To deselect all nodes, press  and click anywhere on the background of the automation track.



Limiting the Movement of Nodes

Logic “intelligently” analyses the direction of mouse movements, making the control over nodes in the Track Automation data much easier.

In cases where the mouse is initially moved in one direction—vertically or horizontally—the move is “limited” to this direction. This makes it easy to retain the node(s) value(s) while changing the position(s), or to keep the position(s) while

changing the value(s). If the mouse is moved on the other plane in the X-Y axis (horizontally or vertically), the directional “limit” will be overridden and you can freely position the node(s).

You can, of course, limit the movement of nodes to one direction.

- If you press  while changing the value, the selected node(s) is limited to *horizontal* movement.
- If you press  while changing the value, the selected node(s) is limited to *vertical* movement.

Handling Lines



Lines are created automatically between nodes. The following “node” functions are pertinent to lines.


- a short click on, or just outside, a line (not a node) will add a new node on the line.
- a long click on a line allows you to move the line, along with its two endpoints—i.e. the nodes that encompass the line.
- a long click outside a line will create and select a new node, allowing you to move that node immediately.

Curves

There may be occasions where you wish to create nonlinear automation data.


- Linear means a straight line.
- Nonlinear means curved.


Click-holding on a line or a selection, with   depressed, allows you to set various curves on a line or the current selection.



Four types of curve shapes are available. These can be set by moving the mouse different directions:

- horizontal S-Curve
- vertical S-Curve
- convex
- concave


The most useful shape when changing the level is the *horizontal S-Curve*. Click on a line with  **ctrl** depressed and move the mouse to the right.


A short click while holding down  **ctrl** on a line or a selection will reset the curve of the current line or current selection to linear—i.e. a straight line.

Please experiment with these.




Selection Handling

The following functions affect a selected area (selection) of visible automation data allowing you to cut, copy and move it.




Hold  and rubber-band select nodes 4 through to 8, as shown in the diagram, to try out these functions.




Delete

- Press the  key to delete the current selection.
- Select **Edit > Undo Clear** or use the   Key Command, to reverse the deletion.

Copy

- Hold down  and click-hold on the selected area (this also works on lines and nodes). Drag the selected section to bar 21 on the right to copy it.
- Select **Edit > Undo HyperDraw** or use the   Key Command, to undo the copy.

Move

- Deselect the area by clicking quickly on the background of the selected area.
- Now, hold down  and move your mouse cursor to a position just before node 5—bar 11.
- Click hold at this position and you'll notice that all data from the current mouse position through to the last node is selected. It can be freely moved horizontally or vertically.
- If you release the mouse button (but keep the keys depressed) and click at a position after node 5, the selection area will change.

Moved or copied automation data will automatically erase any data which exists in the destination area. This works “intelligently” with non-contiguous selections.

Important!

Why not apply the techniques you’ve learned about multiple selections and moving or copying automation data to see this “intelligence” in action?

4.8 The Final Mix

The Introduction Manual has introduced you to the basic information you will need to effectively record, arrange, edit and automate the mix of your audio and MIDI tracks.


The last step in the recording process is often referred to as the “(final) mix” or “mixdown” of your song. It contains:

- Audio Tracks
- Audio Instrument Tracks
- MIDI Tracks—recorded as audio files
- Any effects used on these tracks
- Automation of levels, pan positions, mutes and effect parameters etc. throughout the song

To facilitate your “mixdown”, Logic features a **Bnce** (*Bounce*) button at the bottom of the Master Fader in the Track Mixer.



The “final mix” or *Bounce*, as it is known in Logic, is a real-time, digital process. The entire song—or a section of it defined by the left and right *locators*—is played. All mix automation data *of tracks routed to the selected Master Fader* is performed in realtime as the song is played back. These “mixed” and effected Audio tracks and Audio Instruments are combined into a single mono or stereo file. Mono/Stereo status is determined by the button beside the **Bnce** button.

 It is also possible to *Bounce* to a number of discrete files for Surround sound purposes. Please consult the Logic Reference manual for further information.

Bouncing—Procedure

This section presumes that all Audio and Audio Instrument tracks have been recorded, arranged and have effects inserted or bussed appropriately. Any automation data for these tracks is also presumed to be “complete”.

- Open the Track Mixer. Don’t forget to make use of the various view buttons to the left of the window.
- Ensure that all Audio, Audio Instrument and/or Bus channels are routed to the desired Master fader.
- Ensure that the Automation *Mode* status is set to **Read, Touch** or **Latch** on each Audio, Audio Instrument and/or Bus channel that features automation track data.
- Click the **Bnce** button on the desired Master Fader (if you have audio hardware with more than one output pair). This will usually be “Output 1-2” or “Master 1”. The following window will launch.



- Check that the **Start** and **End** positions are correct. By default, they will encompass the area from the beginning of the first audio region to the last audio region. You may wish to add an extra bar or so to the **End** position to ensure that you capture any Reverb “tails” or Delay repeats, if applicable.
- Select the other parameters—**Resolution, File Format, File-type** as desired, by click holding in each flip menu panel. Further information on these parameters is available in the Logic 5 Addendum and Reference manual.

- Press the **Bnce** button and an operating system File Save dialog window will open. Browse to the desired folder, and name the file.
- Press **Save** and the bounce will commence.
- Once completed, the bounced file will be available for your use in CD-burning applications, Logic or other applications.

About MIDI Sequences and Tracks

MIDI sequences or tracks will not be *bounced* unless they have been recorded as audio files and assigned to Audio Tracks. There is a common misconception of users new to MIDI and digital audio recording that MIDI can be “converted” to audio. As outlined in the first chapter, MIDI and audio data are very different.

If your song contains MIDI sequences (played by your synthesizers, modules etc.) that you would like to include in your final mix, simply record them as you would any audio source. Once recorded as an audio file, you are free to insert effects, or perform any other process available for audio files and regions in Logic.

As a tip, we recommend that you record each MIDI part as a separate audio file. Use the track or sequence **Mute** or **Solo** functions, the locators and other techniques you’ve learned, to simplify the task. The advantage of keeping your MIDI tracks separate—and this can include individual drum sounds in a “kit”—is that you can individually process these sounds/parts. This gives you far more creative flexibility, and control, during the mixing process.

Tip


Bounce—Saving Resources

It should be noted that the *bounce* procedure is a very processor and disk-intensive task. It requires additional processing resources due to the fact that a new audio file is calculated and written, in addition to the playback of your various tracks and effects. The following collection of tips may assist you with your *bounces*.

- To check the status of your CPU resources before and during a *bounce*, please select the **Audio > System Performance** meter. This gives you an overview of the CPU and disk usage.
- Deselect any Audio Instrument tracks in the Track List—i.e. select a MIDI track.
- *Mute* any unused tracks in the Track List. Remember that **Mute** can be automated, so make use of this when parts are not playing.
- Disable the **Catch** function in all open windows, or better yet, close all windows except the Track Mixer.
- *Bypass* all unused effects. Remember that **Bypass** can be automated, so make use of this ability when the effect is not needed.
- For grouped fade ins or outs, use a *Bus* or *Master* fader, rather than automating each channel individually. It is more CPU-efficient and less labor intensive.
- Bouncing 24 Bit files is more disk-intensive. If bouncing for CD-delivery, use 16 Bit, 44.1 kHz.
- If your system is close to its processing limits with the playback duties alone, you may need to perform two discrete *bounce* processes, combining the resultant file of the first *bounce* with the remaining unbounced tracks. Use the **Solo** and **Mute** functions, or the *Outputs* or *Buses* to facilitate this.

4.9 Audio Configuration

While not strictly a “mixing” function, you may wish to experiment with or change your effects routings. You may also wish to quickly change the routing of your Audio and Audio Instrument tracks. While these tasks can be performed in the Track Mixer, Logic features an additional window which gives you an overview of your audio configuration. It is launched by selecting the **Audio > Audio Configuration** menu option.



A portion of the Audio Configuration window is shown above. It provides you with an overview of your Audio objects.

Once launched, the **View** menu provides you with options to view **All** or **All Used Components**.

The two Tools allow you to insert, remove, bypass and move effects. Please experiment with them.

The **Edit** menu provides you with options to **Remove EQ's**, **Plug-Ins**, **Sends** and the **Record Path**. The **Edit** menu also provides you with the usual cut, copy and paste functions. We'll allow you to experiment with these on your own, and ask that you take into account the following:

- Remove allows you to strip out all unused/unwanted effects by type.
- Cut, copy and paste functions work between songs.

When combined, you can quickly strip down one set of effects and/or routings from a song, and apply this routing configuration to another song.

Chapter 5

Miscellaneous Info

First up, we'd like to congratulate you on working your way through the Introduction Manual. At this stage, you should be reasonably comfortable with the basic working methods, windows and terminology of Logic. You're probably also ready to get started on your own musical ideas and productions.

5.1 The Autoload Song

We ask that you re-load your Autoload song now. Feel free to make any desired changes to the Preferences, Screensets and Key Commands that you may have picked up, while working through the Introduction Manual. These don't have to be made right now, but keep them in mind. It's probable that you'll change your working methods as you become more familiar with the program. Remember that as you do, you should incorporate these changes into your Autoload song by changing the song Preferences and Screensets. Changes made to Key Commands and Global Preferences affect Logic at a program-wide level. Such changes are saved in a separate file which resides in your *Preferences* folder.

The Autoload song is the template for all of your future work. When starting a new project, the first thing you should do after Logic has launched, and (auto)loaded your Autoload song is to:

- Use the **File > Save As...** function, and give it a different name (and select the appropriate folder path, as desired).
- Following this, you're ready to go.

Please make use of the Introduction Manual and Reference manual if you need to jog your memory on working methods, or on customizing your Autoload.

The other topics in this chapter briefly cover the integration of Logic with external software and hardware.

5.2 SoundDiver

SoundDiver is a program, manufactured by Emagic, that provides editing control and storage (librarian) facilities for MIDI devices. It supports well over 500 devices including: synthesizers, effects units, MIDI controlled mixers, samplers and more.

SoundDiver features a unique ability to “interrogate” MIDI devices and to extract information about sounds, patches and settings from them. This information is then categorized and stored in a *library* file.

When run at the same time as Logic, the information extracted by SoundDiver can be passed on to Logic’s Environment as a set of patch names for each device.

This is handled by a dynamic internal “bridge” between the two programs called *Autolink*.

About Autolink

The *Autolink* facility provides much more than the simple exchanging of patch names between SoundDiver and Logic. It also allows any realtime changes made in SoundDiver’s MIDI device editors to be recorded directly to the currently selected track in Logic.

Autolink is enabled in Logic by selecting the **Options > Settings > MIDI Interface Communication > Use AUTOLINK with SoundDiver or SoundSurfer if available** checkbox.

Using Autolink

Logic must be launched *before* SoundDiver.

Important!


When both programs are launched, and Autolink is active, Logic handles all MIDI inputs and outputs.

- Any MIDI data arriving at a MIDI IN port will be routed via Logic to SoundDiver.
- SoundDiver's MIDI output is routed via Logic to a MIDI OUT port.
- SoundDiver's MIDI THRU sends the incoming data to the currently selected MIDI device.

SoundDiver will automatically scan the currently loaded Logic song for an *Instrument* object in the Environment which matches the MIDI port, and channel settings, of the MIDI device presently selected in SoundDiver. If no matching *Instrument* object exists in Logic, you'll be asked if you'd like to create one.

This facility is ideal when setting up Logic for the first time. You can simply allow SoundDiver to scan all of your MIDI ports. Once it finds and interrogates all of your MIDI devices, the patch name information of the devices is passed on to Logic.

This information is dynamic, so any changes you make in SoundDiver are communicated to Logic, automatically updating the patch name lists for each *Instrument* object.

 It should be noted that the changes made to names in SoundDiver are not saved with the *Instrument* objects in the Logic song. This means that you will always need to run SoundDiver alongside Logic when loading this song. Alternately, you can manually make changes to the *Instrument* objects through use of the *Update via Autolink* function. More information on this is available in the Logic Reference manual.

5.3 Logic Control

As the name suggests, Logic Control provides “control” over Logic Platinum’s (version 5 and higher) many functions. The Logic Control XT is an expansion unit which adds additional channels.

The immediate benefit of using the Logic Control is that recording, mixing and editing tasks are greatly accelerated, as you have simultaneous “hands-on” control over multiple channels and/or parameters. These include; transport, scrubbing, mute, solo, volume, pan, plug-in parameters, screensets—in fact, any “control” you can think of. This control over multiple channels/parameters is more convenient than use of the mouse, which is limited to one task at a time.



Any changes made by you on the Logic Control’s surface are reflected in Logic, in realtime. When these changes are recorded and played back, the Logic Control will physically update to “follow” the automation. Its motorized faders will move smoothly as fades are played back, the main display and the LED’s for each switch will update in realtime to indicate their current value.

The Logic Control and *each* Logic Control XT unit (if applicable) must have a discrete MIDI IN and MIDI OUT connection to a free, dedicated MIDI port on your MIDI interface. We recommend the use of the Emagic Unitor8, AMT8 or MT4 interfaces.

Important!

When Logic Platinum 5 (or higher) is launched, it will automatically “sense” the Logic Control unit(s) and will send information about the current program and song settings. The current song position and parameter values will appear on the Logic Control’s displays.

The faders, knobs and switches on the Logic Control and XT units do not have fixed functions or channels. This allows you to switch between fader “banks”, or to increment in channels. To explain, audio channels 1—8 would be bank 1, audio channels 9—16 would be bank 2 a.s.o. Incrementing by channel could allow the switching between plug-ins where all 8 faders and knobs are assigned to the parameters of the plug-in. As an example, two instances of the **ES2** synthesizer are inserted on Audio Instrument “channels” 3 and 4. Switching by channel allows you to toggle between the two. As you do so, the status of all relevant faders, knobs, switches and displays will update to reflect your current selection.

As new functions are added to future versions of Logic, the Logic Control unit(s) will automatically receive this information each time Logic is launched. This ensures that the Logic Control units will remain “current” for many years to come.

For further details on the Logic Control and it’s integration with Logic, please visit our website at www.emagic.de

5.4 Synchronization

Logic Platinum and Gold feature extensive synchronization facilities. These facilities allow you to “lock” Logic to film and video, drum machines, other sequencers, digital audio workstations (DAW’s) and more. Logic can act as the *Master*—controlling the timing of the slave—or *Slave*—where Logic follows the timing of the master.

Logic Audio (formerly Silver) is limited to MIDI Time Code (MTC) and MIDI Clock synchronization. This means it can only be synchronized with devices which communicate their timing information via MIDI.

When synchronized, transport controls such as start, stop or continue are sent from the Master to the Slave. Timing information about the current bar/beat, or an “absolute time” position is also sent. Absolute time is measured on a 24 hour clock and is divided into hours, minutes, seconds, frames, sub-frames. The frames and sub-frames come from the use of synchronization with film. This terminology and technology was dreamed up by the Society of Motion Picture and Television Engineers (SMPTE).

- Absolute time is more commonly known as SMPTE time code. This type of synchronization is only available in Logic Gold or Platinum.
- MIDI Time Code (MTC) is the MIDI world’s equivalent of SMPTE time code. It is available to all Logic versions.
- MIDI Clock is a simple timing pulse which is sent out. It does not contain any positional information, but does send start and stop messages.



The Transport Bar changed to display the current SMPTE (absolute time) position. This is achieved by clicking on the “down” arrow to the right of the display. From left to right it displays hours, minutes, seconds, frames, sub-frames.

The Logic Reference manual covers the specifics of each synchronization parameter, and their use, which we'll allow you to view at your leisure.

Synchronization Tips

If you are running an external MIDI device that is capable of sending MIDI Clock or MIDI Time Code (MTC) messages (Drum Machine, Sequencer, Workstation keyboard etc.) then you may encounter strange error messages or odd “stuttering” behavior in Logic. To rectify the problem, try these tips—one at a time:

- Open the **Options > Settings > Synchronization Settings > General** menu/page. Uncheck the **Transmit MIDI Clock** and **Transmit MTC** options which will stop a “loop” of MIDI synchronization data occurring.
- In the **Options > Settings > Synchronization Settings > MIDI** menu page, you can specify a port for synchronization data if you wish to send it to a specific device, but not to all of your devices.
- Check your digital clock settings (if applicable to your setup). Please consult the separate Installation Guide, and your audio interface documentation, for further information.

That concludes the Logic Introduction Manual.

Please make use of the Reference manual and our online resources at www.emagic.de Our international distribution team and dealer network are also available to assist you with any sales or technical queries you may have.

We wish you many years of successful music making, inspiration and enjoyment with Logic.

We will continue to bring you the very best in music technology and look forward to a long and fruitful creative partnership with you.

Your Emagic Team.

